

Infinispan 13.0 Server Guide

Table of Contents

1. Getting started with Infinispan Server	2
1.1. Infinispan Server requirements	2
1.2. Downloading Infinispan Server distributions	2
1.3. Installing Infinispan Server	2
1.4. Starting Infinispan Server	3
1.5. Creating and modifying Infinispan users	3
1.5.1. Adding credentials	4
1.5.2. Assigning roles to users	4
1.5.3. Adding users to groups	5
1.5.4. User roles and permissions	6
1.6. Verifying cluster views	6
1.7. Shutting down Infinispan Server	7
1.7.1. Infinispan cluster restarts	8
1.8. Infinispan Server installation directory structure	8
1.8.1. Server root directory	9
2. Creating remote caches	11
2.1. Default cache manager	11
2.2. Creating caches with Infinispan Console	12
2.3. Creating remote caches with the Infinispan CLI	12
2.4. Creating remote caches from Hot Rod clients	13
2.5. Creating remote caches with the REST API	14
3. Network interfaces and socket bindings	15
3.1. Network interfaces	15
3.2. Socket bindings	17
3.3. Changing the bind address for Infinispan Server	18
3.3.1. Listening on all addresses	19
3.4. Infinispan Server ports and protocols	20
3.4.1. Configuring network firewalls for Infinispan traffic	21
3.5. Specifying port offsets	21
4. Server endpoints	22
4.1. Hot Rod	22
4.2. REST	22
4.3. Memcached	23
4.4. Comparison of endpoint protocols	23
4.5. Endpoint connectors	23
4.6. Configuring multiple endpoints	24
4.7. Infinispan Server endpoint IP address filters	25
4.8. Inspecting and modifying rules for filtering IP addresses	26

5. Security realms	27
5.1. Property security realms	27
5.2. LDAP security realms	29
5.2.1. LDAP realm principal re-writing	33
5.3. Token security realms	35
5.4. Trust store security realms	37
5.5. Distributed security realms	40
6. Configuring Endpoint Authentication Mechanisms	42
6.1. Infinispan Server Authentication	42
6.2. Manually Configuring Hot Rod Authentication	44
6.2.1. Hot Rod authentication	44
6.2.2. Hot Rod authentication mechanisms	45
6.2.3. SASL quality of protection (QoP)	46
6.2.4. SASL policies for Hot Rod authentication	46
6.3. Manually Configuring REST Authentication	47
6.3.1. REST authentication	48
6.3.2. REST authentication mechanisms	48
6.4. Disabling Authentication	49
7. Encrypting Infinispan Server Connections	50
7.1. Configuring Infinispan Server Keystores	50
7.1.1. Automatically Generating Keystores	51
7.1.2. Configuring TLS versions and cipher suites	52
7.2. Configuring Client Certificate Authentication	53
7.3. Configuring Authorization with Client Certificates	56
8. Configuring Kerberos Identities for Infinispan Server	57
8.1. Setting Up Kerberos Identities	57
8.2. Kerberos Identity Configuration	58
9. Storing Infinispan Server Credentials in Keystores	59
9.1. Setting Up Credential Keystores	59
9.2. Credential Keystore Configuration	60
10. Configuring User Authorization	65
10.1. Enabling Authorization in Cache Configuration	65
10.2. User roles and permissions	65
10.3. How Security Authorization Works	66
10.3.1. Permissions	67
10.3.2. Role Mappers	68
10.4. Access Control List (ACL) Cache	69
10.5. Customizing Roles and Permissions	70
10.6. Disabling Security Authorization	71
10.7. Configuring Authorization with Client Certificates	71
11. Setting up Infinispan cluster transport	72

11.1. Default JGroups stacks	72
11.2. Cluster discovery protocols	73
11.2.1. PING	73
11.2.2. TCPPING	73
11.2.3. MPING	74
11.2.4. TCPGOSSIP	74
11.2.5. JDBC_PING	75
11.2.6. DNS_PING	75
11.2.7. Cloud discovery protocols	75
11.3. Using the default JGroups stacks	76
11.4. Customizing JGroups stacks	77
11.4.1. Inheritance attributes	78
11.5. Using JGroups system properties	79
11.5.1. Cluster transport properties	79
11.5.2. System properties for cloud discovery protocols	80
11.6. Using inline JGroups stacks	81
11.7. Using external JGroups stacks	82
11.8. Encrypting cluster transport	83
11.8.1. Securing cluster transport with TLS identities	83
11.8.2. JGroups encryption protocols	84
11.8.3. Securing cluster transport with asymmetric encryption	85
11.8.4. Securing cluster transport with symmetric encryption	87
11.9. TCP and UDP ports for cluster traffic	88
12. Configuring Infinispan Server with managed datasources	89
12.1. Configuring Infinispan Server with managed datasources	89
12.2. Managed datasources for JDBC connections	90
13. Remotely Executing Server-Side Tasks	94
13.1. Creating Server Tasks	94
13.1.1. Server Tasks	94
13.1.2. Deploying Server Tasks to Infinispan Servers	95
13.2. Creating Server Scripts	96
13.2.1. Server Scripts	96
13.2.2. Adding Scripts to Infinispan Servers	98
13.2.3. Programmatically Creating Scripts	99
13.3. Running Server-Side Tasks and Scripts	99
13.3.1. Running Tasks and Scripts	99
13.3.2. Programmatically Running Scripts	99
13.3.3. Programmatically Running Tasks	100
14. Enabling and Customizing Logging	101
14.1. Server Logs	101
14.1.1. Configuring Server Logs	101

14.1.2. Log Levels	101
14.1.3. Infinispan Log Categories	102
14.1.4. Log Appenders	102
14.1.5. Log Patterns	103
14.1.6. Enabling and Configuring the JSON Log Handler	103
14.2. Access Logs	104
14.2.1. Enabling Access Logs	104
14.2.2. Access Log Properties	104
14.3. Audit Logs	105
14.3.1. Enabling Audit Logging	105
14.3.2. Configuring Audit Logging Appenders	106
14.3.3. Using Custom Audit Logging Implementations	106
15. Enabling and configuring Infinispan statistics and JMX monitoring	108
15.1. Enabling statistics in remote caches	108
15.2. Enabling Hot Rod client statistics	108
15.3. Configuring Infinispan metrics	109
15.4. Registering JMX MBeans	111
15.4.1. Enabling JMX remote ports	112
15.4.2. Infinispan MBeans	112
15.4.3. Registering MBeans in custom MBean servers	112
16. Retrieving Health Statistics	114
16.1. Accessing the Health API via JMX	114
16.2. Accessing the Health API via REST	114
17. Performing rolling upgrades for Infinispan Server clusters	116
17.1. Setting up target Infinispan clusters	116
17.2. Synchronizing data to target clusters	118
18. Patching Infinispan Server Installations	119
18.1. Infinispan Server Patches	119
18.2. Creating Server Patches	119
18.3. Installing Server Patches	120
18.4. Rolling Back Server Patches	121
19. Troubleshooting Infinispan Servers	123
19.1. Getting Diagnostic Reports for Infinispan Servers	123
19.2. Changing Infinispan Server Logging Configuration at Runtime	123
19.3. Resource Statistics	125

Infinispan Server deployments offer distributed remote caches with elastic scalability and high performance access.

Chapter 1. Getting started with Infinispan Server

Quickly set up Infinispan Server and learn the basics.

[Get started icon] You can also visit our [Get Started with Infinispan](#) tutorial and run the server image in 4 easy steps.

1.1. Infinispan Server requirements

Infinispan Server requires a Java Virtual Machine and works with Java 11 and later.



Infinispan Server does not support Java 8. However, you can use Java 8 with Hot Rod Java clients.

1.2. Downloading Infinispan Server distributions

The Infinispan Server distribution is an archive of Java libraries (**JAR** files) and configuration files.

Procedure

1. Download Infinispan 13.0 Server from [Infinispan downloads](#).
2. Run the `sha1sum` command with the server download archive as the argument, for example:

```
$ sha1sum infinispan-server-{version}.zip
```

3. Compare with the **SHA-1** checksum value on the Infinispan downloads page.

Reference

The Infinispan Server README, available in the distribution, provides example commands for running the server, describes folders in the `$ISPN_HOME` directory, and lists system properties you can use to customize the filesystem.

1.3. Installing Infinispan Server

Install the Infinispan Server distribution on a host system.

Prerequisites

- Download a Infinispan Server distribution archive.

Procedure

- Use any appropriate tool to extract the Infinispan Server archive to the host filesystem.

```
$ unzip infinispan-server-13.0.4.Final.zip
```

The resulting directory is your `$ISPN_HOME`.

1.4. Starting Infinispan Server

Run Infinispan Server instances in a Java Virtual Machine (JVM).

Prerequisites

- Download and install the server distribution.

Procedure

1. Open a terminal in `$ISPN_HOME`.
2. Start Infinispan Server instances with the `server` script.

Linux

```
$ bin/server.sh
```

Microsoft Windows

```
bin\server.bat
```

Infinispan Server is running successfully when it logs the following messages:

```
ISPN080004: Protocol SINGLE_PORT listening on 127.0.0.1:11222
ISPN080034: Server '...' listening on http://127.0.0.1:11222
ISPN080001: Infinispan Server <version> started in <mm>ms
```

Verification

1. Open `127.0.0.1:11222/console/` in any browser.
2. Enter your credentials at the prompt and continue to Infinispan Console.

1.5. Creating and modifying Infinispan users

Add Infinispan user credentials and assign permissions to control access to data.

Infinispan server installations use a property realm to authenticate users for the Hot Rod and REST endpoints. This means you need to create at least one user before you can access Infinispan.

By default, users also need roles with permissions to access caches and interact with Infinispan resources. You can assign roles to users individually or add users to groups that have role permissions.

You create users and assign roles with the `user` command in the Infinispan command line interface (CLI).



Run `help user` from a CLI session to get complete command details.

1.5.1. Adding credentials

You need an `admin` user for the Infinispan Console and full control over your Infinispan environment. For this reason you should create a user with `admin` permissions the first time you add credentials.

Procedure

1. Open a terminal in `$ISPN_HOME`.
2. Create an `admin` user with the `user create` command.
 - Add a user assigned to the `admin` group.

```
$ bin/cli.sh user create myuser -p changeme -g admin
```

- Use implicit authorization to gain `admin` permissions.

```
$ bin/cli.sh user create admin -p changeme
```

3. Open `user.properties` and `groups.properties` with any text editor to verify users and groups.

```
$ cat server/conf/users.properties

#$REALM_NAME=default$
#$ALGORITHM=encrypted$
myuser=scram-sha-1\:BYGcIAwvf6b...

$ cat server/conf/groups.properties

myuser=admin
```

1.5.2. Assigning roles to users

Assign roles to users so they have the correct permissions to access data and modify Infinispan resources.

Procedure

1. Start a CLI session with an `admin` user.

```
$ bin/cli.sh
```

2. Assign the `deployer` role to "katie".

```
[//containers/default]> user roles grant --roles=deployer katie
```

3. List roles for "katie".

```
[//containers/default]> user roles ls katie  
["deployer"]
```

1.5.3. Adding users to groups

Groups let you change permissions for multiple users. You assign a role to a group and then add users to that group. Users inherit permissions from the group role.

Procedure

1. Start a CLI session with an **admin** user.
2. Use the **user create** command to create a group.
 - a. Specify "developers" as the group name with the **--groups** argument.
 - b. Set a username and password for the group.

In a property realm, a group is a special type of user that also requires a username and password.

```
[//containers/default]> user create --groups=developers developers -p changeme
```

3. List groups.

```
[//containers/default]> user ls --groups  
["developers"]
```

4. Assign the **application** role to the "developers" group.

```
[//containers/default]> user roles grant --roles=application developers
```

5. List roles for the "developers" group.

```
[//containers/default]> user roles ls developers  
["application"]
```

6. Add existing users, one at a time, to the group as required.

```
[//containers/default]> user groups john --groups=developers
```

1.5.4. User roles and permissions

Infinispan includes a default set of roles that grant users with permissions to access data and interact with Infinispan resources.

`ClusterRoleMapper` is the default mechanism that Infinispan uses to associate security principals to authorization roles.



`ClusterRoleMapper` matches principal names to role names. A user named `admin` gets `admin` permissions automatically, a user named `deployer` gets `deployer` permissions, and so on.

Role	Permissions	Description
<code>admin</code>	ALL	Superuser with all permissions including control of the Cache Manager lifecycle.
<code>deployer</code>	ALL_READ, ALL_WRITE, LISTEN, EXEC, MONITOR, CREATE	Can create and delete Infinispan resources in addition to <code>application</code> permissions.
<code>application</code>	ALL_READ, ALL_WRITE, LISTEN, EXEC, MONITOR	Has read and write access to Infinispan resources in addition to <code>observer</code> permissions. Can also listen to events and execute server tasks and scripts.
<code>observer</code>	ALL_READ, MONITOR	Has read access to Infinispan resources in addition to <code>monitor</code> permissions.
<code>monitor</code>	MONITOR	Can view statistics via JMX and the <code>metrics</code> endpoint.

Reference

- [org.infinispan.security.AuthorizationPermission Enumeration](#)
- [Infinispan configuration schema reference](#)

1.6. Verifying cluster views

Infinispan Server instances on the same network automatically discover each other and form clusters.

Complete this procedure to observe cluster discovery with the `MPING` protocol in the default `TCP` stack with locally running Infinispan Server instances. If you want to adjust cluster transport for custom network requirements, see the documentation for setting up Infinispan clusters.



This procedure is intended to demonstrate the principle of cluster discovery and is not intended for production environments. Doing things like specifying a port offset on the command line is not a reliable way to configure cluster transport for production.

Prerequisites

Have one instance of Infinispan Server running.

Procedure

1. Open a terminal in `$ISPAN_HOME`.
2. Copy the root directory to `server2`.

```
$ cp -r server server2
```

3. Specify a port offset and the `server2` directory.

```
$ bin/server.sh -o 100 -s server2
```

Verification

You can view cluster membership in the console at `127.0.0.1:11222/console/cluster-membership`.

Infinispan also logs the following messages when nodes join clusters:

```
INFO [org.infinispan.CLUSTER] (jgroups-11,<server_hostname>)
ISPN000094: Received new cluster view for channel cluster:
[<server_hostname>|3] (2) [<server_hostname>, <server2_hostname>]

INFO [org.infinispan.CLUSTER] (jgroups-11,<server_hostname>)
ISPN100000: Node <server2_hostname> joined the cluster
```

1.7. Shutting down Infinispan Server

Stop individually running servers or bring down clusters gracefully.

Procedure

1. Create a CLI connection to Infinispan.
2. Shut down Infinispan Server in one of the following ways:
 - Stop all nodes in a cluster with the `shutdown cluster` command, for example:

```
[//containers/default]> shutdown cluster
```

This command saves cluster state to the `data` folder for each node in the cluster. If you use a

cache store, the `shutdown cluster` command also persists all data in the cache.

- Stop individual server instances with the `shutdown server` command and the server hostname, for example:

```
[//containers/default]> shutdown server <my_server01>
```



The `shutdown server` command does not wait for rebalancing operations to complete, which can lead to data loss if you specify multiple hostnames at the same time.



Run `help shutdown` for more details about using the command.

Verification

Infinispan logs the following messages when you shut down servers:

```
ISPN080002: Infinispan Server stopping
ISPN000080: Disconnecting JGroups channel cluster
ISPN000390: Persisted state, version=<$version> timestamp=YYYY-MM-DDTHH:MM:SS
ISPN080003: Infinispan Server stopped
```

1.7.1. Infinispan cluster restarts

When you bring Infinispan clusters back online after shutting them down, you should wait for the cluster to be available before adding or removing nodes or modifying cluster state.

If you shutdown clustered nodes with the `shutdown server` command, you must restart each server in reverse order.

For example, if you shutdown `server1` and then shutdown `server2`, you should first start `server2` and then start `server1`.

If you shutdown a cluster with the `shutdown cluster` command, clusters become fully operational only after all nodes rejoin.

You can restart nodes in any order but the cluster remains in DEGRADED state until all nodes that were joined before shutdown are running.

1.8. Infinispan Server installation directory structure

Infinispan Server uses the following folders on the host filesystem under `$ISPN_HOME`:

```
|— bin
|— boot
|— docs
|— lib
|— server
|— static
```



See the Infinispan Server README, available in the distribution, for descriptions of the each folder in your `$ISPN_HOME` directory as well as system properties you can use to customize the filesystem.

1.8.1. Server root directory

Apart from resources in the `bin` and `docs` folders, the only folder under `$ISPN_HOME` that you should interact with is the server root directory, which is named `server` by default.

You can create multiple nodes under the same `$ISPN_HOME` directory or in different directories, but each Infinispan Server instance must have its own server root directory. For example, a cluster of 5 nodes could have the following server root directories on the filesystem:

```
|— server
|— server1
|— server2
|— server3
|— server4
```

Each server root directory should contain the following folders:

```
|— server
|   |— conf
|   |— data
|   |— lib
|   |— log
```

`server/conf`

Holds `infinispan.xml` configuration files for a Infinispan Server instance.

Infinispan separates configuration into two layers:

Dynamic

Create mutable cache configurations for data scalability.

Infinispan Server permanently saves the caches you create at runtime along with the cluster state that is distributed across nodes. Each joining node receives a complete cluster state that Infinispan Server synchronizes across all nodes whenever changes occur.

Static

Add configuration to `infinispan.xml` for underlying server mechanisms such as cluster transport, security, and shared datasources.

server/data

Provides internal storage that Infinispan Server uses to maintain cluster state.



Never directly delete or modify content in `server/data`.

Modifying files such as `caches.xml` while the server is running can cause corruption. Deleting content can result in an incorrect state, which means clusters cannot restart after shutdown.

server/lib

Contains extension `JAR` files for custom filters, custom event listeners, JDBC drivers, custom `ServerTask` implementations, and so on.

server/log

Holds Infinispan Server log files.

Chapter 2. Creating remote caches

When you create remote caches at runtime, Infinispan Server synchronizes your configuration across the cluster so that all nodes have a copy. For this reason you should always create remote caches dynamically with the following mechanisms:

- Infinispan Console
- Infinispan Command Line Interface (CLI)
- Hot Rod or HTTP clients

2.1. Default cache manager

Infinispan Server provides a default cache manager to control the lifecycle of remote caches. Starting Infinispan Server automatically instantiates the cache manager so you can create and delete remote caches and other resources like Protobuf schema.

Default cache manager

```
<infinispan>
  <!-- Creates a cache manager named "default" that exports metrics. -->
  <cache-container name="default"
    statistics="true">
    <!-- Adds cluster transport that uses the default JGroups TCP stack. -->
    <transport cluster="${infinispan.cluster.name:cluster}"
      stack="${infinispan.cluster.stack:tcp}"
      node-name="${infinispan.node.name:}"/>
  </cache-container>
</infinispan>
```

After you start Infinispan Server and add user credentials, you can view details about the cache manager and get cluster information from Infinispan Console.

- Open `127.0.0.1:11222` in any browser.

You can also get information about the cache manager through the Command Line Interface (CLI) or REST API:

CLI

Run the `describe` command in the default container.

```
[//containers/default]> describe
```

REST

Open `127.0.0.1:11222/rest/v2/cache-managers/default/` in any browser.

2.2. Creating caches with Infinispan Console

Use Infinispan Console to create remote caches in an intuitive visual interface from any web browser.

Prerequisites

- Create a Infinispan user with `admin` permissions.
- Start at least one Infinispan Server instance.
- Have a Infinispan cache configuration.

Procedure

1. Open `127.0.0.1:11222/console/` in any browser.
2. Select **Create Cache** and follow the steps as Infinispan Console guides you through the process.

2.3. Creating remote caches with the Infinispan CLI

Use the Infinispan Command Line Interface (CLI) to add remote caches on Infinispan Server.

Prerequisites

- Create a Infinispan user with `admin` permissions.
- Start at least one Infinispan Server instance.
- Have a Infinispan cache configuration.

Procedure

1. Start the CLI and enter your credentials when prompted.

```
$ bin/cli.sh
```

2. Use the `create cache` command to create remote caches.

For example, create a cache named "mycache" from a file named `mycache.xml` as follows:

```
[//containers/default]> create cache --file=mycache.xml mycache
```

Verification

1. List all remote caches with the `ls` command.

```
[//containers/default]> ls caches  
mycache
```

2. View cache configuration with the `describe` command.

```
[//containers/default]> describe caches/mycache
```

2.4. Creating remote caches from Hot Rod clients

Use the Infinispan Hot Rod API to create remote caches on Infinispan Server from Java, C++, .NET/C#, JS clients and more.

This procedure shows you how to use Hot Rod Java clients that create remote caches on first access. You can find code examples for other Hot Rod clients in the [Infinispan Tutorials](#).

Prerequisites

- Create a Infinispan user with `admin` permissions.
- Start at least one Infinispan Server instance.
- Have a Infinispan cache configuration.

Procedure

- Invoke the `remoteCache()` method as part of your the `ConfigurationBuilder`.
- Set the `configuration` or `configuration_uri` properties in the `hotrod-client.properties` file on your classpath.

ConfigurationBuilder

```
File file = new File("path/to/infinispan.xml")
ConfigurationBuilder builder = new ConfigurationBuilder();
builder.remoteCache("another-cache")
    .configuration("<distributed-cache name=\"another-cache\"/>");
builder.remoteCache("my.other.cache")
    .configurationURI(file.toURI());
```

hotrod-client.properties

```
infinispan.client.hotrod.cache.another-cache.configuration=<distributed-cache
name=\"another-cache\"/>
infinispan.client.hotrod.cache.[my.other.cache].configuration_uri=file:///path/to/infi
nispan.xml
```



If the name of your remote cache contains the `.` character, you must enclose it in square brackets when using `hotrod-client.properties` files.

Additional resources

- [Hot Rod Client Configuration](#)
- `org.infinispan.client.hotrod.configuration.RemoteCacheConfigurationBuilder`

2.5. Creating remote caches with the REST API

Use the Infinispan REST API to create remote caches on Infinispan Server from any suitable HTTP client.

Prerequisites

- Create a Infinispan user with **admin** permissions.
- Start at least one Infinispan Server instance.
- Have a Infinispan cache configuration.

Procedure

- Invoke **POST** requests to `/rest/v2/caches/<cache_name>` with cache configuration in the payload.

Additional resources

- [Creating and Managing Caches with the REST API](#)

Chapter 3. Network interfaces and socket bindings

Expose Infinispan Server through a network interface by binding it to an IP address. You can then configure endpoints to use the interface so Infinispan Server can handle requests from remote client applications.

3.1. Network interfaces

Infinispan Server multiplexes endpoints to a single TCP/IP port and automatically detects protocols of inbound client requests. You can configure how Infinispan Server binds to network interfaces to listen for client requests.

Internet Protocol (IP) address

```
<!-- Selects a specific IPv4 address, which can be public, private, or loopback.
      This is the default network interface for Infinispan Server. -->
<interfaces>
  <interface name="public">
    <inet-address value="{infinispan.bind.address:127.0.0.1}"/>
  </interface>
</interfaces>
```

Loopback address

```
<!-- Selects an IP address in an IPv4 or IPv6 loopback address block. -->
<interfaces>
  <interface name="public">
    <loopback/>
  </interface>
</interfaces>
```

Non-loopback address

```
<!-- Selects an IP address in an IPv4 or IPv6 non-loopback address block. -->
<interfaces>
  <interface name="public">
    <non-loopback/>
  </interface>
</interfaces>
```

Any address

```
<!-- Uses the 'INADDR_ANY' wildcard address which means Infinispan Server
      listens for inbound client requests on all interfaces. -->
<interfaces>
  <interface name="public">
    <any-address/>
  </interface>
</interfaces>
```

Link local

```
<!-- Selects a link-local IP address in an IPv4 or IPv6 address block. -->
<interfaces>
  <interface name="public">
    <link-local/>
  </interface>
</interfaces>
```

Site local

```
<!-- Selects a site-local (private) IP address in an IPv4 or IPv6 address block. -->
<interfaces>
  <interface name="public">
    <site-local/>
  </interface>
</interfaces>
```

Match and fallback strategies

Infinispan Server can enumerate all network interfaces on the host system and bind to an interface, host, or IP address that matches a value, which can include regular expressions for additional flexibility.

Match host

```
<!-- Selects an IP address that is assigned to a matching host name. -->
<interfaces>
  <interface name="public">
    <match-host value="my_host_name"/>
  </interface>
</interfaces>
```

Match interface

```
<!--Selects an IP address assigned to a matching network interface. -->
<interfaces>
  <interface name="public">
    <match-interface value="eth0"/>
  </interface>
</interfaces>
```

Match address

```
<!-- Selects an IP address that matches a regular expression. -->
<interfaces>
  <interface name="public">
    <match-address value="132\..*" />
  </interface>
</interfaces>
```

Fallback

```
<!-- Includes multiple strategies that Infinispan Server tries in the
      declared order until it finds a match. -->
<interfaces>
  <interface name="public">
    <match-host value="my_host_name" />
    <match-address value="132\..*" />
    <any-address />
  </interface>
</interfaces>
```

3.2. Socket bindings

Socket bindings map endpoint connectors to server interfaces and ports.

Default socket bindings

```
<socket-bindings default-interface="public"
  port-offset="{infinispan.socket.binding.port-offset:0}">
  <socket-binding name="default"
    port="{infinispan.bind.port:11222}" />
  <socket-binding name="memcached"
    port="11221" />
</socket-bindings>
```

Socket binding configuration attribute	Description
<code>socket-bindings</code>	Declares the default interface and port offset.

Socket binding configuration attribute	Description
default	Binds to Hot Rod and REST connectors to the default port 11222.
memcached	Binds the memcached connector to port 11221 and is disabled by default.

Custom socket binding declarations

The following example configuration adds an `interface` declaration named "private" and a `socket-binding` declaration that binds Infinispan Server to the private IP address:

```
<server xmlns="urn:infinispan:server:13.0">
  <interfaces>
    <interface name="private">
      <inet-address value="10.1.2.3"/>
    </interface>
  </interfaces>

  <socket-bindings default-interface="public" port-offset=
    "${infinispan.socket.binding.port-offset:0}">
    <socket-binding name="private_binding"
      interface="private"
      port="1234"/>
  </socket-bindings>
</server>
```

3.3. Changing the bind address for Infinispan Server

Infinispan Server binds to a network IP address to listen for inbound client connections on the Hot Rod and REST endpoints. You can specify that IP address directly in your Infinispan Server configuration or when starting server instances.

Prerequisites

- Have at least one Infinispan Server installation.

Procedure

Specify the IP address to which Infinispan Server binds in one of the following ways:

- Open your Infinispan Server configuration and set the value for the `inet-address` element, for example:

```
<server xmlns="urn:infinispan:server:13.0">
  <interfaces>
    <interface name="custom">
      <inet-address value="{infinispan.bind.address:192.0.2.0}"/>
    </interface>
  </interfaces>
</server>
```

- Use the `-b` option or the `infinispan.bind.address` system property.

Linux

```
$ bin/server.sh -b 192.0.2.0
```

Windows

```
bin\server.bat -b 192.0.2.0
```

3.3.1. Listening on all addresses

If you specify the `0.0.0.0` meta-address, or `INADDR_ANY`, as the bind address in your Infinispan Server configuration, it listens for incoming client connections on all available network interfaces.

Client intelligence

Configuring Infinispan to listen on all addresses affects how it provides Hot Rod clients with cluster topology. If there are multiple interfaces to which Infinispan Server binds, then it sends a list of IP addresses for each interface.

For example, a cluster where each server node binds to:

- `10.0.0.0/8` subnet
- `192.168.0.0/16` subnet
- `127.0.0.1` loopback

Hot Rod clients receive IP addresses for server nodes that belong to the interface through which the clients connect. If a client connects to `192.168.0.0`, for example, it does not receive any cluster topology details for nodes that listen on `10.0.0.0`.

Netmask override

Kubernetes, and some other environments, divide the IP address space into subnets and use those different subnets as a single network. For example, `10.129.2.100/23` and `10.129.4.100/23` are in different subnets but belong to the `10.0.0.0/8` network.

For this reason, Infinispan Server overrides netmasks that the host system provides with netmasks that follow IANA conventions for private networks:

- IPv4: `10.0.0.0/8`, `192.168.0.0/16`, `172.16.0.0/16`, and `169.254.0.0/16`

- IPv6: `fc00::/7` and `fe80::/10`

See [RFC 1918](#) for IPv4 or [RFC 4193](#) and [RFC 3513](#) for IPv6.



You can optionally configure the Hot Rod connector to use the netmask that the host system provides for interfaces with the `network-prefix-override` attribute in your Infinispan Server configuration.

Additional resources

- [Infinispan Server schema reference](#)
- [RFC 1918](#)
- [RFC 4193](#)
- [RFC 3513](#)

3.4. Infinispan Server ports and protocols

Infinispan Server provides network endpoints that allow client access with different protocols.

Port	Protocol	Description
11222	TCP	Hot Rod and REST
11221	TCP	Memcached (disabled by default)

Single port

Infinispan Server exposes multiple protocols through a single TCP port, 11222. Handling multiple protocols with a single port simplifies configuration and reduces management complexity when deploying Infinispan clusters. Using a single port also enhances security by minimizing the attack surface on the network.

Infinispan Server handles HTTP/1.1, HTTP/2, and Hot Rod protocol requests from clients via the single port in different ways.

HTTP/1.1 upgrade headers

Client requests can include the `HTTP/1.1 upgrade` header field to initiate HTTP/1.1 connections with Infinispan Server. Client applications can then send the `Upgrade: protocol` header field, where `protocol` is a server endpoint.

Application-Layer Protocol Negotiation (ALPN)/Transport Layer Security (TLS)

Client requests include Server Name Indication (SNI) mappings for Infinispan Server endpoints to negotiate protocols over a TLS connection.



Applications must use a TLS library that supports the ALPN extension. Infinispan uses WildFly OpenSSL bindings for Java.

Automatic Hot Rod detection

Client requests that include Hot Rod headers automatically route to Hot Rod endpoints.

3.4.1. Configuring network firewalls for Infinispan traffic

Adjust firewall rules to allow traffic between Infinispan Server and client applications.

Procedure

On Red Hat Enterprise Linux (RHEL) workstations, for example, you can allow traffic to port **11222** with `firewalld` as follows:

```
# firewall-cmd --add-port=11222/tcp --permanent
success
# firewall-cmd --list-ports | grep 11222
11222/tcp
```

To configure firewall rules that apply across a network, you can use the `nftables` utility.

3.5. Specifying port offsets

Configure port offsets for multiple Infinispan Server instances on the same host. The default port offset is **0**.

Procedure

Use the `-o` switch with the Infinispan CLI or the `infinispan.socket.binding.port-offset` system property to set port offsets.

For example, start a server instance with an offset of **100** as follows. With the default configuration, this results in the Infinispan server listening on port **11322**.

Linux

```
$ bin/server.sh -o 100
```

Windows

```
bin\server.bat -o 100
```

Chapter 4. Server endpoints

Infinispan Server endpoints provide client access to the cache manager over Hot Rod and REST protocols.

4.1. Hot Rod

Hot Rod is a binary TCP client-server protocol designed to provide faster data access and improved performance in comparison to text-based protocols.

Infinispan provides Hot Rod client libraries in Java, C++, C#, Node.js and other programming languages.

Topology state transfer

Infinispan uses topology caches to provide clients with cluster views. Topology caches contain entries that map internal JGroups transport addresses to exposed Hot Rod endpoints.

When client send requests, Infinispan servers compare the topology ID in request headers with the topology ID from the cache. Infinispan servers send new topology views if client have older topology IDs.

Cluster topology views allow Hot Rod clients to immediately detect when nodes join and leave, which enables dynamic load balancing and failover.

In distributed cache modes, the consistent hashing algorithm also makes it possible to route Hot Rod client requests directly to primary owners.

Additional resources

- [Infinispan Hot Rod Server](#)
- [Hot Rod client implementations](#)

4.2. REST

Infinispan exposes a RESTful interface that allows HTTP clients to access data, monitor and maintain clusters, and perform administrative operations.

You can use standard HTTP load balancers to provide clients with load balancing and failover capabilities. However, HTTP load balancers maintain static cluster views and require manual updates when cluster topology changes occur.

Additional resources

- [Infinispan REST Server](#)
- [mod_cluster HTTP load balancer](#)

4.3. Memcached

Infinispan provides an implementation of the Memcached text protocol for remote client access.



The Memcached endpoint is deprecated and planned for removal in a future release.

The Infinispan Memcached endpoint supports clustering with replicated and distributed cache modes.

There are some Memcached client implementations, such as the `Cache::Memcached` Perl client, that can offer load balancing and failover detection capabilities with static lists of Infinispan server addresses that require manual updates when cluster topology changes occur.

Additional resources

- [Infinispan Memcached Server](#)
- [Memcached text protocol](#)

4.4. Comparison of endpoint protocols

	Hot Rod	HTTP / REST	Memcached
Topology-aware	Y	N	N
Hash-aware	Y	N	N
Encryption	Y	Y	N
Authentication	Y	Y	N
Conditional ops	Y	Y	Y
Bulk ops	Y	N	N
Transactions	Y	N	N
Listeners	Y	N	N
Query	Y	Y	N
Execution	Y	N	N
Cross-site failover	Y	N	N

4.5. Endpoint connectors

Connectors configure Infinispan Server endpoints with socket bindings and security realms

Default endpoint connector

```
<endpoints socket-binding="default" security-realm="default"/>
```

The default endpoint connector implicitly configures Hot Rod and REST endpoints with a socket

binding and security realm.

Endpoint configuration attribute	Description
<code>endpoints</code>	Wraps endpoint connector configuration.
<code>endpoint</code>	Declares a Infinispan Server endpoint that configures Hot Rod and REST connectors.
<code>hotrod-connector</code>	Configures how clients connect to Infinispan Server over the Hot Rod protocol.
<code>rest-connector</code>	Configures how clients connect to Infinispan Server over the REST/HTTP protocol.
<code>memcached-connector</code>	Configures how clients connect to Infinispan Server over Memcached, which is disabled by default.

Additional resources

- [Infinispan schema reference](#)

4.6. Configuring multiple endpoints

You can configure multiple Infinispan Server endpoints to bind to different sockets and use different security realms.

Prerequisites

- Configure socket bindings for endpoints.
- Configure security realms for endpoints.

Procedure

1. Open your Infinispan Server configuration for editing.
2. Wrap multiple `endpoint` configurations with the `endpoints` element.
3. Specify the socket binding for each endpoint with the `socket-binding` attribute.
4. Specify the security realm for each endpoint with the `security-realm` attribute.
5. If necessary disable administrative capabilities, such as Infinispan Console and Command Line Interface (CLI), for an endpoint with the `admin="false"` attribute.
6. Include `hotrod-connector` and `rest-connector` configurations for each endpoint.
7. Save and close your Infinispan Server configuration.

Multiple endpoint configuration

The following Infinispan Server configuration enables two endpoints on separate socket bindings with dedicated security realms:

```
<endpoints>
  <endpoint socket-binding="public"
            security-realm="application-realm"
            admin="false">
    <hotrod-connector/>
    <rest-connector/>
  </endpoint>
  <endpoint socket-binding="private"
            security-realm="management-realm">
    <hotrod-connector/>
    <rest-connector/>
  </endpoint>
</endpoints>
```

Additional resources

- [Network interfaces and socket bindings](#)

4.7. Infinispan Server endpoint IP address filters

Infinispan endpoints and connectors can specify one or more IP filtering rules. These rules specify the type of action to take when a client which matches a supplied CIDR block connects. IP filtering rules are applied in order up until the first one that matches.

A CIDR block is a compact representation of an IP address and its associated network mask. CIDR notation specifies an IP address, a slash (/) character, and a decimal number. The decimal number is the count of leading 1 bits in the network mask. The number can also be thought of as the width, in bits, of the network prefix. The IP address in CIDR notation is always represented according to the standards for IPv4 or IPv6.

The address can denote a specific interface address, including a host identifier, such as `10.0.0.1/8`, or it can be the beginning address of an entire network interface range using a host identifier of 0, as in `10.0.0.0/8` or `10/8`.

For example:

- `192.168.100.14/24` represents the IPv4 address `192.168.100.14` and its associated network prefix `192.168.100.0`, or equivalently, its subnet mask `255.255.255.0`, which has 24 leading 1-bits.
- the IPv4 block `192.168.100.0/22` represents the 1024 IPv4 addresses from `192.168.100.0` to `192.168.103.255`.
- the IPv6 block `2001:db8::/48` represents the block of IPv6 addresses from `2001:db8:0:0:0:0:0:0` to `2001:db8:0:ffff:ffff:ffff:ffff:ffff`.
- `::1/128` represents the IPv6 loopback address. Its prefix length is 128 which is the number of bits in the address.

```

<endpoints>
  <endpoint socket-binding="default" security-realm="default">
    <ip-filter>
      <accept from="192.168.0.0/16"/>
      <accept from="10.0.0.0/8"/>
      <reject from="/0"/>
    </ip-filter>
    <hotrod-connector name="hotrod"/>
    <rest-connector name="rest"/>
  </endpoint>
</endpoints>

```

As a result of the preceding configuration, Infinispan Server accepts connections only from addresses in the `192.168.0.0/16` and `10.0.0.0/8` CIDR blocks. Infinispan Server rejects all other connections.

4.8. Inspecting and modifying rules for filtering IP addresses

Configure IP address filtering rules on Infinispan Server endpoints to accept or reject connections based on client address.

Prerequisites

- Install Infinispan Command Line Interface (CLI).

Procedure

1. Create a CLI connection to Infinispan Server.
2. Inspect and modify the IP filter rules `server connector ipfilter` command as required.
 - a. List all IP filtering rules active on a connector across the cluster:

```
[//containers/default]> server connector ipfilter ls endpoint-default
```

- b. Set IP filtering rules across the cluster.



This command replaces any existing rules.

```
[//containers/default]> server connector ipfilter set endpoint-default
--rules=ACCEPT/192.168.0.0/16,REJECT/10.0.0.0/8`
```

- c. Remove all IP filtering rules on a connector across the cluster.

```
[//containers/default]> server connector ipfilter clear endpoint-default
```

Chapter 5. Security realms

Security realms define identity, encryption, authentication, and authorization configuration for Infinispan Server endpoints.

5.1. Property security realms

Property realms use property files to define users and groups.

`users.properties` maps usernames to passwords in plain-text format. Passwords can also be pre-digested if you use the `DIGEST-MD5` SASL mechanism or `Digest` HTTP mechanism.

```
myuser=a_password
user2=another_password
```

`groups.properties` maps users to roles.

```
myuser=supervisor,reader,writer
user2=supervisor
```

Endpoint authentication mechanisms

When you configure Infinispan Server to use a property realm, you can configure endpoints to use the following authentication mechanisms:

- Hot Rod (SASL): `PLAIN`, `DIGEST-*`, and `SCRAM-*`
- REST (HTTP): `Basic` and `Digest`

Property realm configuration

XML

```
<security xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
          xsi:schemaLocation="urn:infinispan:server:13.0
https://infinispan.org/schemas/infinispan-server-13.0.xsd"
          xmlns="urn:infinispan:server:13.0">
  <security-realms>
    <security-realm name="default">
      <!-- Defines groups as roles for server authorization. -->
      <properties-realm groups-attribute="Roles">
        <!-- Specifies the properties file that holds usernames and passwords. -->
        <!-- The plain-text="true" attribute stores passwords in plain text. -->
        <user-properties path="users.properties"
                        relative-to="infinispan.server.config.path"
                        plain-text="true"/>
        <!-- Specifies the properties file that defines roles for users. -->
        <group-properties path="groups.properties"
                          relative-to="infinispan.server.config.path"/>
      </properties-realm>
    </security-realm>
  </security-realms>
</security>
```

JSON

```
{
  "security": {
    "security-realms": [
      {
        "name": "default",
        "properties-realm": {
          "groups-attribute": "Roles",
          "user-properties": {
            "path": "ServerConfigurationParserTest-user.properties",
            "relative-to": "infinispan.server.config.path",
            "plain-text": true
          },
          "group-properties": {
            "path": "ServerConfigurationParserTest-group.properties",
            "relative-to": "infinispan.server.config.path"
          }
        }
      }
    ]
  }
}
```

```

security:
  security-realms:
    - name: default
      properties-realm:
        groups-attribute: Roles
        user-properties:
          digest-realm-name: digest
          path: 'ServerConfigurationParserTest-user.properties'
          relative-to: 'infinispan.server.config.path'
          plain-text: true
        group-properties:
          path: 'ServerConfigurationParserTest-group.properties'
          relative-to: 'infinispan.server.config.path'

```

5.2. LDAP security realms

LDAP realms connect to LDAP servers, such as OpenLDAP, Red Hat Directory Server, Apache Directory Server, or Microsoft Active Directory, to authenticate users and obtain membership information.



LDAP servers can have different entry layouts, depending on the type of server and deployment. It is beyond the scope of this document to provide examples for all possible configurations.

Endpoint authentication mechanisms

When you configure Infinispan Server to use an LDAP realm, you can configure endpoints to use the following authentication mechanisms:

- Hot Rod (SASL): **PLAIN**, **DIGEST-***, and **SCRAM-***
- REST (HTTP): **Basic** and **Digest**

LDAP realm configuration

```

<security xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
  xsi:schemaLocation="urn:infinispan:server:13.0
https://infinispan.org/schemas/infinispan-server-13.0.xsd"
  xmlns="urn:infinispan:server:13.0">
  <security-realms>
    <security-realm name="default">
      <!-- Names an LDAP realm and specifies connection properties. -->
      <ldap-realm name="ldap"
        url="ldap://my-ldap-server:10389"
        principal="uid=admin,ou=People,dc=infinispan,dc=org"
        credential="strongPassword"
        connection-timeout="3000"
        read-timeout="30000"
        connection-pooling="true"
        referral-mode="ignore"
        page-size="30"
        direct-verification="true">
        <!-- Defines how principals are mapped to LDAP entries. -->
        <identity-mapping rdn-identifier="uid"
          search-dn="ou=People,dc=infinispan,dc=org"
          search-recursive="false">
          <!-- Retrieves all the groups of which the user is a member. -->
          <attribute-mapping>
            <attribute from="cn"
              to="Roles"
              filter="(objectClass=groupOfNames)(member={1})"
              filter-dn="ou=Roles,dc=infinispan,dc=org"/>
          </attribute-mapping>
        </identity-mapping>
      </ldap-realm>
    </security-realm>
  </security-realms>
</security>

```

```
{
  "security": {
    "security-realms": [
      {
        "name": "default",
        "ldap-realm": {
          "url": "ldap://my-ldap-server:10389",
          "principal": "uid=admin,ou=People,dc=infinispan,dc=org",
          "credential": "strongPassword",
          "connection-timeout": "3000",
          "read-timeout": "30000",
          "connection-pooling": "true",
          "referral-mode": "ignore",
          "page-size": "30",
          "direct-verification": "true",
          "identity-mapping": {
            "rdn-identifier": "uid",
            "search-dn": "ou=People,dc=infinispan,dc=org",
            "search-recursive": "false",
            "attribute-mapping": [
              {
                "from": "cn",
                "to": "Roles",
                "filter": "(&(objectClass=groupOfNames)(member={1}))",
                "filter-dn": "ou=Roles,dc=infinispan,dc=org"
              }
            ]
          }
        }
      }
    ]
  }
}
```

```

security:
  security-realms:
    - name: default
      ldap-realm:
        name: ldap
        url: 'ldap://my-ldap-server:10389'
        principal: 'uid=admin,ou=People,dc=infinispan,dc=org'
        credential: strongPassword
        connection-timeout: '3000'
        read-timeout: '30000'
        connection-pooling: true
        referral-mode: ignore
        page-size: '30'
        direct-verification: true
        identity-mapping:
          rdn-identifier: uid
          search-dn: 'ou=People,dc=infinispan,dc=org'
          search-recursive: false
          attribute-mapping:
            - filter: '(&(objectClass=groupOfNames)(member={1}))'
              filter-dn: 'ou=Roles,dc=infinispan,dc=org'
              from: cn
              to: Roles

```



The principal for LDAP connections must have necessary privileges to perform LDAP queries and access specific attributes.

As an alternative to verifying user credentials with the `direct-verification` attribute, you can specify an LDAP password with the `user-password-mapper` element.

The `rdn-identifier` attribute specifies an LDAP attribute that finds the user entry based on a provided identifier, which is typically a username; for example, the `uid` or `sAMAccountName` attribute. Add `search-recursive="true"` to the configuration to search the directory recursively. By default, the search for the user entry uses the `(rdn_identifier={0})` filter. Specify a different filter with the `filter-name` attribute.

The `attribute-mapping` element retrieves all the groups of which the user is a member. There are typically two ways in which membership information is stored:

- Under group entries that usually have class `groupOfNames` in the `member` attribute. In this case, you can use an attribute filter as in the preceding example configuration. This filter searches for entries that match the supplied filter, which locates groups with a `member` attribute equal to the user's DN. The filter then extracts the group entry's CN as specified by `from`, and adds it to the user's `Roles`.
- In the user entry in the `memberOf` attribute. In this case you should use an attribute reference such as the following:

```
<attribute-reference reference="memberOf" from="cn" to="Roles" />
```

This reference gets all `memberOf` attributes from the user's entry, extracts the CN as specified by `from`, and adds them to the user's `Roles`.

5.2.1. LDAP realm principal re-writing

Some SASL authentication mechanisms, such as `GSSAPI`, `GS2-KRB5` and `Negotiate`, supply a username that needs to be *cleaned up* before you can use it to search LDAP servers.

XML

```
<security xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
  xsi:schemaLocation="urn:infinispan:server:13.0
https://infinispan.org/schemas/infinispan-server-13.0.xsd"
  xmlns="urn:infinispan:server:13.0">
  <security-realms>
    <security-realm name="default">
      <ldap-realm name="ldap"
        url="ldap://${org.infinispan.test.host.address}:10389"
        principal="uid=admin,ou=People,dc=infinispan,dc=org"
        credential="strongPassword">
        <name-rewriter>
          <!-- Defines a rewriter that extracts the username from the principal
using a regular expression. -->
          <regex-principal-transformer name="domain-remover"
            pattern="(.*@INFINISPAN\.ORG"
            replacement="$1"/>
        </name-rewriter>
        <identity-mapping rdn-identifier="uid"
          search-dn="ou=People,dc=infinispan,dc=org">
          <attribute-mapping>
            <attribute from="cn" to="Roles"
              filter="((&,(objectClass=groupOfNames)(member={1}))"
              filter-dn="ou=Roles,dc=infinispan,dc=org" />
          </attribute-mapping>
          <user-password-mapper from="userPassword" />
        </identity-mapping>
      </ldap-realm>
    </security-realm>
  </security-realms>
</security>
```

```

{
  "security": {
    "security-realms": [
      {
        "name": "default",
        "ldap-realm": {
          "url": "ldap://my-ldap-server:10389",
          "principal": "uid=admin,ou=People,dc=infinispan,dc=org",
          "credential": "strongPassword",
          "identity-mapping": {
            "rdn-identifier": "uid",
            "search-dn": "ou=People,dc=infinispan,dc=org",
            "name-rewriter": {
              "regex-principal-transformer": {
                "pattern": "(.*)@INFINISPAN\\.ORG",
                "replacement": "$1"
              }
            },
            "attribute-mapping": [
              {
                "from": "cn",
                "to": "Roles",
                "filter": "(&(objectClass=groupOfNames)(member={1}))",
                "filter-dn": "ou=Roles,dc=infinispan,dc=org"
              }
            ],
            "user-password-mapper": {
              "from": "userPassword"
            }
          }
        }
      }
    ]
  }
}

```

```

security:
  security-realms:
    - name: default
      ldap-realm:
        name: ldap
        url: 'ldap://my-ldap-server:10389'
        principal: 'uid=admin,ou=People,dc=infinispan,dc=org'
        credential: strongPassword
        name-rewriter:
          regex-principal-transformer:
            name: 'domain-remover'
            pattern: (.*)@INFINISPAN\.ORG
            replacement: $1
        identity-mapping:
          rdn-identifier: uid
          search-dn: 'ou=People,dc=infinispan,dc=org'
          attribute-mapping:
            - filter: '(&(objectClass=groupOfNames)(member={1}))'
              filter-dn: 'ou=Roles,dc=infinispan,dc=org'
              from: cn
              to: Roles
        user-password-mapper:
          from: userPassword

```

5.3. Token security realms

Token realms use external services to validate tokens and require providers that are compatible with RFC-7662 (OAuth2 Token Introspection), such as KeyCloak.

Endpoint authentication mechanisms

When you configure Infinispan Server to use a token realm, you must configure endpoints to use the following authentication mechanisms:

- Hot Rod (SASL): `OAUTHBEARER`
- REST (HTTP): `Bearer`

Token realm configuration

XML

```
<security xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
  xsi:schemaLocation="urn:infinispan:server:13.0
https://infinispan.org/schemas/infinispan-server-13.0.xsd"
  xmlns="urn:infinispan:server:13.0">
  <security-realms>
    <security-realm name="default">
      <!-- Specifies the URL of the authentication server. -->
      <token-realm name="token"
        auth-server-url="https://oauth-server/auth/">
        <!-- Specifies the URL of the token introspection endpoint. -->
        <oauth2-introspection
          introspection-url="https://oauth-
server/auth/realms/infinispan/protocol/openid-connect/token/introspect"
          client-id="infinispan-server"
          client-secret="1fdca4ec-c416-47e0-867a-3d471af7050f"/>
        </token-realm>
      </security-realm>
    </security-realms>
  </security>
```

JSON

```
{
  "security": {
    "security-realms": [
      {
        "name": "default",
        "token-realm": {
          "name": "token",
          "auth-server-url": "https://oauth-server/auth/",
          "oauth2-introspection": {
            "client-id": "infinispan-server",
            "client-secret": "1fdca4ec-c416-47e0-867a-3d471af7050f",
            "introspection-url": "https://oauth-
server/auth/realms/infinispan/protocol/openid-connect/token/introspect"
          }
        }
      }
    ]
  }
}
```

```

security:
  security-realms:
    - name: default
      token-realm:
        name: token
        auth-server-url: 'https://oauth-server/auth/'
        oauth2-introspection:
          client-id: infinispan-server
          client-secret: '1fdca4ec-c416-47e0-867a-3d471af7050f'
          introspection-url: 'https://oauth-
server/auth/realms/infinispan/protocol/openid-connect/token/introspect'

```

5.4. Trust store security realms

Trust store realms use certificates, or certificates chains, that verify Infinispan Server and client identities when they negotiate connections.

Keystores

Contain server certificates that provide a Infinispan Server identity to clients. If you configure a keystore with server certificates, Infinispan Server encrypts traffic using industry standard SSL/TLS protocols.

Trust stores

Contain client certificates, or certificate chains, that clients present to Infinispan Server. Client trust stores are optional and allow Infinispan Server to perform client certificate authentication.

Client certificate authentication

You must add the `require-ssl-client-auth="true"` attribute to the endpoint configuration if you want Infinispan Server to validate or authenticate client certificates.

Endpoint authentication mechanisms

If you configure Infinispan Server with a keystore only, you can use encryption in combination with any authentication mechanism.

When you configure Infinispan Server to use a client trust store, you must configure endpoints to use the following authentication mechanisms:

- Hot Rod (SASL): `EXTERNAL`
- REST (HTTP): `CLIENT_CERT`

Trust store realm configuration

```

<security xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" xsi:schemaLocation=
"urn:infinispan:server:13.0 https://infinispan.org/schemas/infinispan-server-13.0.xsd"
xmlns="urn:infinispan:server:13.0">
  <security-realms>
    <security-realm name="default">
      <server-identities>
        <ssl>
          <!-- Provides an SSL/TLS identity with a keystore that
              contains server certificates. -->
          <keystore path="server.p12"
                  relative-to="infinispan.server.config.path"
                  keystore-password="secret"
                  alias="server"/>
          <!-- Configures a trust store that contains client certificates
              or part of a certificate chain. -->
          <truststore path="trust.p12"
                    relative-to="infinispan.server.config.path"
                    password="secret"/>
        </ssl>
      </server-identities>
      <!-- Authenticates client certificates against the trust store. If you configure
          this, the trust store must contain the public certificates for all clients. -->
      <truststore-realm/>
    </security-realm>
  </security-realms>
</security>
<!-- Configures Infinispan Server to require client certificates
    with the "require-ssl-client-auth" attribute. -->
<endpoints>
  <endpoint socket-binding="default"
            security-realm="default"
            require-ssl-client-auth="true">
  <hotrod-connector>
    <!-- Configures the Hot Rod endpoint for
        client certificate authentication. -->
    <authentication>
      <sasl mechanisms="EXTERNAL"
              server-name="infinispan"
              qop="auth"/>
    </authentication>
  </hotrod-connector>
  <rest-connector>
    <!-- Configures the REST endpoint for
        client certificate authentication. -->
    <authentication mechanisms="CLIENT_CERT"/>
  </rest-connector>
</endpoint>
</endpoints>

```

```

{
  "security": {
    "security-realms": [
      {
        "name": "default",
        "server-identities": {
          "ssl": {
            "keystore": {
              "path": "server.p12",
              "relative-to": "infinispan.server.config.path",
              "keystore-password": "secret",
              "alias": "server"
            },
            "truststore": {
              "path": "trust.p12",
              "relative-to": "infinispan.server.config.path",
              "password": "secret"
            }
          }
        },
        "truststore-realm": {}
      }
    ]
  },
  "endpoints": [
    {
      "socket-binding": "default",
      "security-realm": "default",
      "require-ssl-client-auth": "true",
      "connectors": {
        "hotrod": {
          "hotrod-connector": {
            "authentication": {
              "sasl": {
                "mechanisms": "EXTERNAL",
                "server-name": "infinispan",
                "qop": "auth"
              }
            }
          }
        },
        "rest": {
          "rest-connector": {
            "authentication": {
              "mechanisms": "CLIENT_CERT"
            }
          }
        }
      }
    }
  ]
}

```

```
}  
]  
}
```

YAML

```
security:  
  security-realms:  
    - name: "default"  
      server-identities:  
        ssl:  
          keystore:  
            path: "server.p12"  
            relative-to: "infinispan.server.config.path"  
            keystore-password: "secret"  
            alias: "server"  
          truststore:  
            path: "trust.p12"  
            relative-to: "infinispan.server.config.path"  
            password: "secret"  
          truststore-realm: ~  
  endpoints:  
    socket-binding: "default"  
    security-realm: "default"  
    require-ssl-client-auth: "true"  
  connectors:  
    - hotrod:  
      hotrod-connector:  
        authentication:  
          sasl:  
            mechanisms: "EXTERNAL"  
            server-name: "infinispan"  
            qop: "auth"  
    - rest:  
      rest-connector:  
        authentication:  
          mechanisms: "CLIENT_CERT"
```

5.5. Distributed security realms

Distributed realms combine multiple security realms. When authenticating users, Infinispan Server uses each security realm in turn until it finds one that can perform the authentication.

Distributed realm configuration

```
<security xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
  xsi:schemaLocation="urn:infinispan:server:13.0
  https://infinispan.org/schemas/infinispan-server-13.0.xsd"
  xmlns="urn:infinispan:server:13.0">
  <security-realms>
    <security-realm name="default">
      <ldap-realm>
        <!-- ... -->
      </ldap-realm>
      <properties-realm>
        <!-- ... -->
      </properties-realm>
      <distributed-realm/> <!-- will use both the ldap and properties realms -->
    </security-realm>
  </security-realms>
</security>
```

Supported authentication mechanisms

Distributed realms support the authentication mechanisms of the underlying realms.

Chapter 6. Configuring Endpoint Authentication Mechanisms

Configure Hot Rod and REST connectors with SASL or HTTP authentication mechanisms to authenticate with clients.

Infinispan servers require user authentication to access the command line interface (CLI) and console as well as the Hot Rod and REST endpoints. Infinispan servers also automatically configure authentication mechanisms based on the security realms that you define.

6.1. Infinispan Server Authentication

Infinispan servers automatically configure authentication mechanisms based on the security realm that you assign to endpoints.

SASL Authentication Mechanisms

The following SASL authentication mechanisms apply to Hot Rod endpoints:

Security Realm	SASL Authentication Mechanism
Property Realms and LDAP Realms	SCRAM-*, DIGEST-*, CRAM-MD5
Token Realms	OAUTHBEARER
Trust Realms	EXTERNAL
Kerberos Identities	GSSAPI, GS2-KRB5
SSL/TLS Identities	PLAIN

HTTP Authentication Mechanisms

The following HTTP authentication mechanisms apply to REST endpoints:

Security Realm	HTTP Authentication Mechanism
Property Realms and LDAP Realms	DIGEST
Token Realms	BEARER_TOKEN
Trust Realms	CLIENT_CERT
Kerberos Identities	SPNEGO
SSL/TLS Identities	BASIC

Default Configuration

Infinispan servers provide a security realm named "default" that uses a property realm with plain text credentials defined in `$ISPN_HOME/server/conf/users.properties`, as shown in the following snippet:

XML

```
<security-realm name="default">
  <properties-realm groups-attribute="Roles">
    <user-properties path="users.properties"
      relative-to="infinispan.server.config.path"
      plain-text="true"/>
    <group-properties path="groups.properties"
      relative-to="infinispan.server.config.path" />
  </properties-realm>
</security-realm>
```

JSON

```
{
  "security-realms": [
    {
      "name": "default",
      "properties-realm": {
        "groups-attribute": "Roles",
        "user-properties": {
          "path": "users.properties",
          "relative-to": "infinispan.server.config.path",
          "plain-text": "true"
        },
        "group-properties": {
          "path": "groups.properties",
          "relative-to": "infinispan.server.config.path"
        }
      }
    }
  ]
}
```

YAML

```
securityRealms:
- name: "default"
  propertiesRealm:
    groupsAttribute: "Roles"
    userProperties:
      path: "users.properties"
      relativeTo: "infinispan.server.config.path"
      plainText: "true"
    groupProperties:
      path: "groups.properties"
      relativeTo: "infinispan.server.config.path"
```

The `endpoints` configuration assigns the "default" security realm to the Hot Rod and REST

connectors, as follows:

XML

```
<endpoints socket-binding="default" security-realm="default"/>
```

JSON

```
{
  "endpoints": [
    {
      "socket-binding": "default",
      "security-realm": "default"
    }
  ]
}
```

YAML

```
endpoints:
- socketBinding: "default"
  securityRealm: "default"
```

As a result of the preceding configuration, Infinispan servers require authentication with a mechanism that the property realm supports.

6.2. Manually Configuring Hot Rod Authentication

Explicitly configure Hot Rod connector authentication to override the default SASL authentication mechanisms that Infinispan servers use for security realms.

Procedure

1. Add an **authentication** definition to the Hot Rod connector configuration.
2. Specify which Infinispan security realm the Hot Rod connector uses for authentication.
3. Specify the SASL authentication mechanisms for the Hot Rod endpoint to use.
4. Configure SASL authentication properties as appropriate.

6.2.1. Hot Rod authentication

```
<endpoints>
  <endpoint socket-binding="default" security-realm="default">
    <hotrod-connector>
      <authentication>
        <!-- Specifies SASL mechanisms to use for authentication. -->
        <!-- Defines the name that the server declares to clients. -->
        <sasl mechanisms="SCRAM-SHA-512 SCRAM-SHA-384 SCRAM-SHA-256
          SCRAM-SHA-1 DIGEST-SHA-512 DIGEST-SHA-384
          DIGEST-SHA-256 DIGEST-SHA DIGEST-MD5 PLAIN"
          server-name="infinispan"
          qop="auth"/>
      </authentication>
    </hotrod-connector>
    <rest-connector />
  </endpoint>
</endpoints>
```

```
<endpoints>
  <endpoint socket-binding="default" security-realm="default">
    <hotrod-connector>
      <authentication>
        <!-- Enables the GSSAPI and GS2-KRB5 mechanisms for Kerberos authentication.
        -->
        <!-- Defines the server name, which is equivalent to the Kerberos service
        name, and specifies the Kerberos identity for the server. -->
        <sasl mechanisms="GSSAPI GS2-KRB5"
          server-name="datagrid"
          server-principal="hotrod/datagrid@INFINISPAN.ORG"/>
      </authentication>
    </hotrod-connector>
    <rest-connector />
  </endpoint>
</endpoints>
```

Additional resources

- [Infinispan schema reference](#)

6.2.2. Hot Rod authentication mechanisms

Infinispan supports the following SASL authentications mechanisms with the Hot Rod connector:

Authentication mechanism	Description	Related details
PLAIN	Uses credentials in plain-text format. You should use PLAIN authentication with encrypted connections only.	Similar to the Basic HTTP mechanism.
DIGEST-*	Uses hashing algorithms and nonce values. Hot Rod connectors support DIGEST-MD5 , DIGEST-SHA , DIGEST-SHA-256 , DIGEST-SHA-384 , and DIGEST-SHA-512 hashing algorithms, in order of strength.	Similar to the Digest HTTP mechanism.
SCRAM-*	Uses <i>salt</i> values in addition to hashing algorithms and nonce values. Hot Rod connectors support SCRAM-SHA , SCRAM-SHA-256 , SCRAM-SHA-384 , and SCRAM-SHA-512 hashing algorithms, in order of strength.	Similar to the Digest HTTP mechanism.
GSSAPI	Uses Kerberos tickets and requires a Kerberos Domain Controller. You must add a corresponding kerberos server identity in the realm configuration. In most cases, you also specify an ldap-realm to provide user membership information.	Similar to the SPNEGO HTTP mechanism.
GS2-KRB5	Uses Kerberos tickets and requires a Kerberos Domain Controller. You must add a corresponding kerberos server identity in the realm configuration. In most cases, you also specify an ldap-realm to provide user membership information.	Similar to the SPNEGO HTTP mechanism.
EXTERNAL	Uses client certificates.	Similar to the CLIENT_CERT HTTP mechanism.
OAUTHBEARER	Uses OAuth tokens and requires a token-realm configuration.	Similar to the BEARER_TOKEN HTTP mechanism.

6.2.3. SASL quality of protection (QoP)

If SASL mechanisms support integrity and privacy protection (QoP) settings, you can add them to your Hot Rod connector configuration with the **qop** attribute.

QoP setting	Description
auth	Authentication only.
auth-int	Authentication with integrity protection.
auth-conf	Authentication with integrity and privacy protection.

6.2.4. SASL policies for Hot Rod authentication

SASL policies control which authentication mechanisms Hot Rod connectors can use.

Policy	Description	Default value
forward-secrecy	Use only SASL mechanisms that support forward secrecy between sessions. This means that breaking into one session does not automatically provide information for breaking into future sessions.	false
pass-credentials	Use only SASL mechanisms that require client credentials.	false
no-plain-text	Do not use SASL mechanisms that are susceptible to simple plain passive attacks.	false
no-active	Do not use SASL mechanisms that are susceptible to active, non-dictionary, attacks.	false
no-dictionary	Do not use SASL mechanisms that are susceptible to passive dictionary attacks.	false
no-anonymous	Do not use SASL mechanisms that accept anonymous logins.	true



Infinispan cache authorization restricts access to caches based on roles and permissions. If you configure cache authorization, you can then set `<no-anonymous value=false />` to allow anonymous login and delegate access logic to cache authorization.

Hot Rod connector with SASL policy configuration

```
<hotrod-connector socket-binding="hotrod" cache-container="default">
  <authentication security-realm="ApplicationRealm">
    <!-- Specifies multiple SASL authentication mechanisms for the Hot Rod
connector. -->
    <sasl server-name="myhotrodserver"
mechanisms="PLAIN DIGEST-MD5 GSSAPI EXTERNAL"
qop="auth">
    <!-- Defines policies for SASL mechanisms. -->
    <policy>
      <no-active value="true" />
      <no-anonymous value="true" />
      <no-plain-text value="true" />
    </policy>
  </sasl>
</authentication>
</hotrod-connector>
```

As a result of the preceding configuration, the Hot Rod connector uses the `GSSAPI` mechanism because it is the only mechanism that complies with all policies.

6.3. Manually Configuring REST Authentication

Explicitly configure REST connector authentication to override the default HTTP authentication mechanisms that Infinispan servers use for security realms.

Procedure

1. Add an **authentication** definition to the REST connector configuration.
2. Specify which Infinispan security realm the REST connector uses for authentication.
3. Specify the authentication mechanisms for the REST endpoint to use.

6.3.1. REST authentication

REST connector with BASIC and DIGEST authentication

```
<endpoints>
  <endpoint socket-binding="default" security-realm="default">
    <hotrod-connector/>
    <rest-connector>
      <!-- Specifies SASL mechanisms to use for authentication. -->
      <authentication mechanisms="DIGEST BASIC"/>
    </rest-connector>
  </endpoint>
</endpoints>
```

REST connector with Kerberos authentication

```
<endpoints>
  <endpoint socket-binding="default" security-realm="default">
    <hotrod-connector/>
    <rest-connector>
      <!-- Enables the `SPENGO` mechanism for Kerberos authentication and specifies an
identity for the server. -->
      <authentication mechanisms="SPNEGO"
server-principal="HTTP/localhost@INFINISPAN.ORG"/>
    </rest-connector>
  </endpoint>
</endpoints>
```

Additional resources

- [Infinispan schema reference](#)

6.3.2. REST authentication mechanisms

Infinispan supports the following authentications mechanisms with the REST connector:

Authentic ation mechanis m	Description	Related details
BASIC	Uses credentials in plain-text format. You should use BASIC authentication with encrypted connections only.	Corresponds to the Basic HTTP authentication scheme and is similar to the PLAIN SASL mechanism.

Authenticat ion mechanis m	Description	Related details
DIGEST	Uses hashing algorithms and nonce values. REST connectors support SHA-512 , SHA-256 and MD5 hashing algorithms.	Corresponds to the Digest HTTP authentication scheme and is similar to DIGEST-* SASL mechanisms.
SPNEGO	Uses Kerberos tickets and requires a Kerberos Domain Controller. You must add a corresponding kerberos server identity in the realm configuration. In most cases, you also specify an ldap-realm to provide user membership information.	Corresponds to the Negotiate HTTP authentication scheme and is similar to the GSSAPI and GS2-KRB5 SASL mechanisms.
BEARER_TOKEN	Uses OAuth tokens and requires a token-realm configuration.	Corresponds to the Bearer HTTP authentication scheme and is similar to OAUTHBEARER SASL mechanism.
CLIENT_CERT	Uses client certificates.	Similar to the EXTERNAL SASL mechanism.

6.4. Disabling Authentication

In local development environments or on isolated networks you can configure Infinispan to allow unauthenticated client requests.

When you disable user authentication you should also disable authorization in your Infinispan security configuration.

Procedure

1. Open `infinispan.xml` for editing.
2. Remove any `security-realm` attributes from the `endpoints` configuration.
3. Ensure that the Hot Rod and REST connectors do not include any `authentication` configuration.

For example, the following configuration allows unauthenticated access to Infinispan:

```
<endpoints socket-binding="default" />
```

4. Remove any `authorization` elements from the `security` configuration for the `cache-container` and each cache configuration.

Chapter 7. Encrypting Infinispan Server Connections

You can secure Infinispan Server connections using SSL/TLS encryption by configuring a keystore that contains public and private keys for Infinispan. You can also configure client certificate authentication if you require mutual TLS.

7.1. Configuring Infinispan Server Keystores

Add keystores to Infinispan Server and configure it to present SSL/TLS certificates that verify its identity to clients. If a security realm contains TLS/SSL identities, it encrypts any connections to Infinispan Server endpoints that use that security realm.

Prerequisites

- Create a keystore that contains certificates, or certificate chains, for Infinispan Server.

Infinispan Server supports the following keystore formats: JKS, JCEKS, PKCS12/PFX and PEM. BKS, BCFKS, and UBER are also supported if the [Bouncy Castle](#) library is present.



In production environments, server certificates should be signed by a trusted Certificate Authority, either Root or Intermediate CA.

Procedure

1. Add the keystore that contains SSL/TLS identities for Infinispan Server to the `$ISPN_HOME/server/conf` directory.
2. Add a `server-identities` definition to the Infinispan Server security realm.
3. Specify the keystore file name with the `path` attribute.
4. Provide the keystore password and certificate alias with the `keystore-password` and `alias` attributes.

```
<security xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
  xsi:schemaLocation="urn:infinispan:server:13.0
https://infinispan.org/schemas/infinispan-server-13.0.xsd"
  xmlns="urn:infinispan:server:13.0">
  <security-realms>
    <security-realm name="default">
      <server-identities>
        <ssl>
          <!-- Adds a keystore that contains server certificates
            that provide SSL/TLS identities to clients. -->
          <keystore path="server.pfx"
            relative-to="infinispan.server.config.path"
            password="secret"
            alias="rhdg-server"/>
        </ssl>
      </server-identities>
    </security-realm>
  </security-realms>
</security>
```



PEM files can be used as keystores provided they contain a private key in PKCS#1 or PKCS#8 format and one or more certificates. These keystores should be configured with an empty password: `password=""`.

Next steps

Configure clients with a trust store so they can verify SSL/TLS identities for Infinispan Server.

Additional resources

- [Configuring Hot Rod client encryption](#)

7.1.1. Automatically Generating Keystores

Configure Infinispan servers to automatically generate keystores at startup.

Automatically generated keystores:



- Should not be used in production environments.
- Are generated whenever necessary; for example, while obtaining the first connection from a client.
- Contain certificates that you can use directly in Hot Rod clients.

Procedure

1. Include the `generate-self-signed-certificate-host` attribute for the `keystore` element in the server configuration.
2. Specify a hostname for the server certificate as the value.


```
<security xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
  xsi:schemaLocation="urn:infinispan:server:13.0
https://infinispan.org/schemas/infinispan-server-13.0.xsd"
  xmlns="urn:infinispan:server:13.0">
  <security-realms>
    <security-realm name="default">
      <server-identities>
        <ssl>
          <!-- Generates a keystore that includes a self-signed certificate with
the specified hostname. -->
          <keystore path="server.p12"
relative-to="infinispan.server.config.path"
keystore-password="secret"
alias="server"
generate-self-signed-certificate-host="localhost"/>
        </ssl>
      </server-identities>
    </security-realm>
  </security-realms>
</security>
```

7.1.2. Configuring TLS versions and cipher suites

When using SSL/TLS encryption to secure your deployment, you can configure Infinispan Server to use specific versions of the TLS protocol as well as specific cipher suites within the protocol.

Procedure

1. Add the `engine` element to the SSL configuration for Infinispan Server.
2. Configure Infinispan to use one or more TLS versions with the `enabled-protocols` attribute.

Infinispan Server supports TLS version 1.2 and 1.3 by default. If appropriate you can set `TLSv1.3` only to restrict the security protocol for client connections. Infinispan does not recommend enabling `TLSv1.1` because it is an older protocol with limited support and provides weak security. You should never enable any version of TLS older than 1.1.



If you modify the SSL `engine` configuration for Infinispan Server you must explicitly configure TLS versions with the `enabled-protocols` attribute. Omitting the `enabled-protocols` attribute allows any TLS version.

```
<engine enabled-protocols="TLSv1.3 TLSv1.2" />
```

3. Configure Infinispan to use one or more cipher suites with the `enabled-ciphersuites` attribute.

You must ensure that you set a cipher suite that supports any protocol features you plan to use; for example `HTTP/2 ALPN`.

```

<security xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
  xsi:schemaLocation="urn:infinispan:server:13.0
  https://infinispan.org/schemas/infinispan-server-13.0.xsd"
  xmlns="urn:infinispan:server:13.0">
  <security-realms>
    <security-realm name="default">
      <server-identities>
        <ssl>
          <keystore path="server.p12"
            relative-to="infinispan.server.config.path"
            keystore-password="secret" alias="server"/>
          <!-- Configures Infinispan Server to use specific TLS versions and
cipher suites. -->
          <engine enabled-protocols="TLSv1.3"
            enabled-ciphersuites="TLS_AES_256_GCM_SHA384
TLS_AES_128_GCM_SHA256 TLS_AES_128_CCM_8_SHA256"/>
        </ssl>
      </server-identities>
    </security-realm>
  </security-realms>
</security>

```

7.2. Configuring Client Certificate Authentication

Configure Infinispan Server to use mutual TLS to secure client connections.

You can configure Infinispan to verify client identities from certificates in a trust store in two ways:

- Require a trust store that contains only the signing certificate, which is typically a Certificate Authority (CA). Any client that presents a certificate signed by the CA can connect to Infinispan.
- Require a trust store that contains all client certificates in addition to the signing certificate. Only clients that present a signed certificate that is present in the trust store can connect to Infinispan.



Alternatively to providing trust stores you can use shared system certificates.

Prerequisites

- Create a client trust store that contains either the CA certificate or all public certificates.
- Create a keystore for Infinispan Server and configure an SSL/TLS identity.



PEM files can be used as trust stores provided they contain one or more certificates. These trust stores should be configured with an empty password: `password=""`.

Procedure

1. Add the `require-ssl-client-auth="true"` parameter to your `endpoints` configuration.
2. Add the client trust store to the `$ISPN_HOME/server/conf` directory.
3. Specify the `path` and `password` attributes for the `truststore` element in the Infinispan Server security realm configuration.
4. Add the `<truststore-realm/>` element to the security realm if you want Infinispan Server to authenticate each client certificate.

```
<security xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" xsi:schemaLocation=
"urn:infinispan:server:13.0 https://infinispan.org/schemas/infinispan-server-13.0.xsd"
xmlns="urn:infinispan:server:13.0">
  <security-realms>
    <security-realm name="default">
      <server-identities>
        <ssl>
          <!-- Provides an SSL/TLS identity with a keystore that
            contains server certificates. -->
          <keystore path="server.p12"
            relative-to="infinispan.server.config.path"
            keystore-password="secret"
            alias="server"/>
          <!-- Configures a trust store that contains client certificates
            or part of a certificate chain. -->
          <truststore path="trust.p12"
            relative-to="infinispan.server.config.path"
            password="secret"/>
        </ssl>
      </server-identities>
      <!-- Authenticates client certificates against the trust store. If you configure
        this, the trust store must contain the public certificates for all clients. -->
      <truststore-realm/>
    </security-realm>
  </security-realms>
</security>
<!-- Configures Infinispan Server to require client certificates
  with the "require-ssl-client-auth" attribute. -->
<endpoints>
  <endpoint socket-binding="default"
    security-realm="default"
    require-ssl-client-auth="true">
  <hotrod-connector>
    <!-- Configures the Hot Rod endpoint for
      client certificate authentication. -->
    <authentication>
      <sasl mechanisms="EXTERNAL"
        server-name="infinispan"
        qop="auth"/>
    </authentication>
  </hotrod-connector>
  <rest-connector>
    <!-- Configures the REST endpoint for
      client certificate authentication. -->
    <authentication mechanisms="CLIENT_CERT"/>
  </rest-connector>
</endpoint>
</endpoints>
```

Next steps

- Set up authorization with client certificates in the Infinispan Server configuration if you control access with security roles and permissions.
- Configure clients to negotiate SSL/TLS connections with Infinispan Server.

Additional resources

- [Configuring Hot Rod client encryption](#)
- [Using Shared System Certificates](#) (Red Hat Enterprise Linux 7 Security Guide)

7.3. Configuring Authorization with Client Certificates

Enabling client certificate authentication means you do not need to specify Infinispan user credentials in client configuration, which means you must associate roles with the Common Name (CN) field in the client certificate(s).

Prerequisites

- Provide clients with a Java keystore that contains either their public certificates or part of the certificate chain, typically a public CA certificate.
- Configure Infinispan Server to perform client certificate authentication.

Procedure

1. Enable the `common-name-role-mapper` in the security authorization configuration.
2. Assign the Common Name (CN) from the client certificate a role with the appropriate permissions.

```
<cache-container name="certificate-authentication" statistics="true">
  <security>
    <authorization>
      <!-- Declare a role mapper that associates the common name (CN) field
           in client certificate trust stores with authorization roles. -->
      <common-name-role-mapper/>
      <!-- In this example, if a client certificate contains `CN=Client1` then
           clients with matching certificates get ALL permissions. -->
      <role name="Client1" permissions="ALL"/>
    </authorization>
  </security>
</cache-container>
```

Chapter 8. Configuring Kerberos Identities for Infinispan Server

Provide Infinispan Server endpoints with Kerberos identities to secure connections with clients.

8.1. Setting Up Kerberos Identities

Kerberos identities use *keytab* files that contain service principal names and encrypted keys, derived from Kerberos passwords.



keytab files can contain both user and service account principals. However, Infinispan servers use service account principals only. As a result, Infinispan servers can provide identity to clients and allow clients to authenticate with Kerberos servers.

In most cases, you create unique principals for the Hot Rod and REST connectors. For example, you have a "datagrid" server in the "INFINISPAN.ORG" domain. In this case you should create the following service principals:

- `hotrod/datagrid@INFINISPAN.ORG` identifies the Hot Rod service.
- `HTTP/datagrid@INFINISPAN.ORG` identifies the REST service.

Procedure

1. Create keytab files for the Hot Rod and REST services.

Linux

```
$ ktutil
ktutil: addent -password -p datagrid@INFINISPAN.ORG -k 1 -e aes256-cts
Password for datagrid@INFINISPAN.ORG: [enter your password]
ktutil: wkt http.keytab
ktutil: quit
```

Microsoft Windows

```
$ ktpass -princ HTTP/datagrid@INFINISPAN.ORG -pass * -mapuser
INFINISPAN\USER_NAME
$ ktab -k http.keytab -a HTTP/datagrid@INFINISPAN.ORG
```

2. Copy the keytab files to the `$ISPN_HOME/server/conf` directory.
3. Add a `server-identities` definition to the Infinispan server security realm.
4. Specify the location of keytab files that provide service principals to Hot Rod and REST connectors.
5. Name the Kerberos service principals.

8.2. Kerberos Identity Configuration

The following example configures Kerberos identities for Infinispan Server:

```
<security xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
  xsi:schemaLocation="urn:infinispan:server:13.0
https://infinispan.org/schemas/infinispan-server-13.0.xsd"
  xmlns="urn:infinispan:server:13.0">
  <security-realms>
    <security-realm name="default">
      <server-identities>
        <!-- Specifies a keytab file that provides a Kerberos identity for the Hot
Rod connector. -->
        <!-- Names the Kerberos service principal for the Hot Rod connector. -->
        <!-- The required="true" attribute specifies that the keytab file must be
present when the server starts. -->
        <kerberos keytab-path="hotrod.keytab"
          principal="hotrod/datagrid@INFINISPAN.ORG"
          required="true"/>
        <!-- Specifies a keytab file that provides a Kerberos identity for the
REST connector. -->
        <!-- Names the Kerberos service principal for the REST connector. -->
        <kerberos keytab-path="http.keytab"
          principal="HTTP/localhost@INFINISPAN.ORG"
          required="true"/>
      </server-identities>
    </security-realm>
  </security-realms>
</security>
```

Chapter 9. Storing Infinispan Server Credentials in Keystores

External services require credentials to authenticate with Infinispan Server. To protect sensitive text strings such as passwords, add them to a credential keystore rather than directly in Infinispan Server configuration files.

You can then configure Infinispan Server to decrypt passwords for establishing connections with services such as databases or LDAP directories.

Plain-text passwords in `$ISPN_HOME/server/conf` are unencrypted. Any user account with read access to the host filesystem can view plain-text passwords.



While credential keystores are password-protected store encrypted passwords, any user account with write access to the host filesystem can tamper with the keystore itself.

To completely secure Infinispan Server credentials, you should grant read-write access only to user accounts that can configure and run Infinispan Server.

9.1. Setting Up Credential Keystores

Create keystores that encrypt credential for Infinispan Server access.

A credential keystore contains at least one alias that is associated with an encrypted password. After you create a keystore, you specify the alias in a connection configuration such as a database connection pool. Infinispan Server then decrypts the password for that alias from the keystore when the service attempts authentication.

You can create as many credential keystores with as many aliases as required.

Procedure

1. Open a terminal in `$ISPN_HOME`.
2. Create a keystore and add credentials to it with the `credentials` command.



By default, keystores are of type PKCS12. Run `help credentials` for details on changing keystore defaults.

The following example shows how to create a keystore that contains an alias of "dbpassword" for the password "changeme". When you create a keystore you also specify a password for the keystore with the `-p` argument.

Linux

```
$ bin/cli.sh credentials add dbpassword -c changeme -p "secret1234!"
```


Microsoft Windows

```
$ bin\cli.bat credentials add dbpassword -c changeme -p "secret1234!"
```

3. Check that the alias is added to the keystore.

```
$ bin/cli.sh credentials ls -p "secret1234!"  
dbpassword
```

4. Configure Infinispan to use the credential keystore.

- a. Specify the name and location of the credential keystore in the `credential-stores` configuration.
- b. Provide the credential keystore and alias in the `credential-reference` configuration.



Attributes in the `credential-reference` configuration are optional.

- `store` is required only if you have multiple keystores.
- `alias` is required only if the keystore contains multiple aliases.

Reference

- [Credential Keystore Configuration](#)

9.2. Credential Keystore Configuration

Review example configurations for credential keystores in Infinispan Server configuration.

Credential keystore

XML

```
<security xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"  
  xsi:schemaLocation="urn:infinispan:server:13.0  
  https://infinispan.org/schemas/infinispan-server-13.0.xsd"  
  xmlns="urn:infinispan:server:13.0">  
  <!-- Uses a keystore to manage server credentials. -->  
  <credential-stores>  
    <!-- Specifies the name and filesystem location of a keystore. -->  
    <credential-store name="credentials" path="credentials.pfx">  
      <!-- Specifies the password for the credential keystore. -->  
      <clear-text-credential clear-text="secret1234!"/>  
    </credential-store>  
  </credential-stores>  
</security>
```

JSON

```
{
  "security": {
    "credential-stores": [
      {
        "name": "credentials",
        "path": "credentials.pfx",
        "clear-text-credential": {
          "clear-text": "secret1234!"
        }
      }
    ]
  }
}
```

YAML

```
security:
  credentialStores:
    - name: credentials
      path: credentials.pfx
      clearTextCredential:
        clearText: "secret1234!"
```

Datasource connection

XML

```
<data-sources xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
  xsi:schemaLocation="urn:infinispan:server:13.0
  https://infinispan.org/schemas/infinispan-server-13.0.xsd"
  xmlns="urn:infinispan:server:13.0">
  <data-source name="postgres" jndi-name="jdbc/postgres">
    <!-- Specifies the database username in the connection factory. -->
    <connection-factory driver="org.postgresql.Driver"
      username="dbuser"
      url="${org.infinispan.server.test.postgres.jdbcUrl}">
      <!-- Specifies the credential keystore that contains an encrypted password
      and the alias for it. -->
      <credential-reference store="credentials" alias="dbpassword"/>
    </connection-factory>
    <connection-pool max-size="10" min-size="1" background-validation="1000" idle-
  removal="1" initial-size="1" leak-detection="10000"/>
  </data-source>
</data-sources>
```

JSON

```
{
  "data-sources": [
    {
      "name": "postgres",
      "jndi-name": "jdbc/postgres",
      "connection-factory": {
        "driver": "org.postgresql.Driver",
        "username": "dbuser",
        "url": "${org.infinispan.server.test.postgres.jdbcUrl}",
        "credential-reference": {
          "store": "credentials",
          "alias": "dbpassword"
        }
      }
    }
  ]
}
```

YAML

```
data-sources:
- name: postgres
  jndiName: jdbc/postgres
  connectionFactory:
    driver: org.postgresql.Driver
    username: dbuser
    url: '${org.infinispan.server.test.postgres.jdbcUrl}'
    credentialReference:
      store: credentials
      alias: dbpassword
```

LDAP connection

```
<security xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
  xsi:schemaLocation="urn:infinispan:server:13.0
https://infinispan.org/schemas/infinispan-server-13.0.xsd"
  xmlns="urn:infinispan:server:13.0">
  <credential-stores>
    <credential-store name="credentials" path="credentials.pfx">
      <clear-text-credential clear-text="secret1234!"/>
    </credential-store>
  </credential-stores>
  <security-realms>
    <security-realm name="default">
      <!-- Specifies the LDAP principal in the connection factory. -->
      <ldap-realm name="ldap" url="ldap://my-ldap-server:10389"
        principal="uid=admin,ou=People,dc=infinispan,dc=org">
        <!-- Specifies the credential keystore that contains an encrypted password
and the alias for it. -->
        <credential-reference store="credentials" alias="ldappassword"/>
      </ldap-realm>
    </security-realm>
  </security-realms>
</security>
```

JSON

```
{
  "security": {
    "credential-stores": [
      {
        "name": "credentials",
        "path": "credentials.pfx",
        "clear-text-credential": {
          "clear-text": "secret1234!"
        }
      }
    ],
    "security-realms": [
      {
        "name": "default",
        "ldap-realm": {
          "name": "ldap",
          "url": "ldap://my-ldap-server:10389",
          "principal": "uid=admin,ou=People,dc=infinispan,dc=org",
          "credential-reference": {
            "store": "credentials",
            "alias": "ldappassword"
          }
        }
      }
    ]
  }
}
```

YAML

```
security:
  credentialStores:
    - name: credentials
      path: credentials.pfx
      clearTextCredential:
        clearText: "secret1234!"
  security-realms:
    - name: "default"
      ldapRealm:
        name: ldap
        url: 'ldap://my-ldap-server:10389'
        principal: 'uid=admin,ou=People,dc=infinispan,dc=org'
        credentialReference:
          store: credentials
          alias: ldappassword
```

Chapter 10. Configuring User Authorization

Authorization is a security feature that requires users to have certain permissions before they can access caches or interact with Infinispan resources. You assign roles to users that provide different levels of permissions, from read-only access to full, super user privileges.

10.1. Enabling Authorization in Cache Configuration

Use authorization in your cache configuration to restrict user access. Before they can read or write cache entries, or create and delete caches, users must have a role with a sufficient level of permission.

Procedure

1. Open your `infinispan.xml` configuration for editing.
2. If it is not already declared, add the `<authorization />` tag inside the `security` elements for the `cache-container`.

This enables authorization for the Cache Manager and provides a global set of roles and permissions that caches can inherit.

3. Add the `<authorization />` tag to each cache for which Infinispan restricts access based on user roles.

The following configuration example shows how to use implicit authorization configuration with default roles and permissions:

```
<infinispan>
  <cache-container default-cache="rbac-cache" name="restricted">
    <security>
      <!-- Enable authorization with the default roles and permissions. -->
      <authorization />
    </security>
    <local-cache name="rbac-cache">
      <security>
        <!-- Inherit authorization settings from the cache-container. -->
        <authorization/>
      </security>
    </local-cache>
  </cache-container>
</infinispan>
```

10.2. User roles and permissions

Infinispan includes a default set of roles that grant users with permissions to access data and interact with Infinispan resources.

`ClusterRoleMapper` is the default mechanism that Infinispan uses to associate security principals to

authorization roles.



`ClusterRoleMapper` matches principal names to role names. A user named `admin` gets `admin` permissions automatically, a user named `deployer` gets `deployer` permissions, and so on.

Role	Permissions	Description
<code>admin</code>	ALL	Superuser with all permissions including control of the Cache Manager lifecycle.
<code>deployer</code>	ALL_READ, ALL_WRITE, LISTEN, EXEC, MONITOR, CREATE	Can create and delete Infinispan resources in addition to <code>application</code> permissions.
<code>application</code>	ALL_READ, ALL_WRITE, LISTEN, EXEC, MONITOR	Has read and write access to Infinispan resources in addition to <code>observer</code> permissions. Can also listen to events and execute server tasks and scripts.
<code>observer</code>	ALL_READ, MONITOR	Has read access to Infinispan resources in addition to <code>monitor</code> permissions.
<code>monitor</code>	MONITOR	Can view statistics via JMX and the <code>metrics</code> endpoint.

Reference

- [org.infinispan.security.AuthorizationPermission Enumeration](#)
- [Infinispan configuration schema reference](#)

10.3. How Security Authorization Works

Infinispan authorization secures your installation by restricting user access.

User applications or clients must belong to a role that is assigned with sufficient permissions before they can perform operations on Cache Managers or caches.

For example, you configure authorization on a specific cache instance so that invoking `Cache.get()` requires an identity to be assigned a role with read permission while `Cache.put()` requires a role with write permission.

In this scenario, if a user application or client with the `io` role attempts to write an entry, Infinispan denies the request and throws a security exception. If a user application or client with the `writer` role sends a write request, Infinispan validates authorization and issues a token for subsequent operations.


Identities

Identities are security Principals of type `java.security.Principal`. Subjects, implemented with the `javax.security.auth.Subject` class, represent a group of security Principals. In other words, a Subject represents a user and all groups to which it belongs.

Identities to roles

Infinispan uses role mappers so that security principals correspond to roles, which you assign one or more permissions.

The following image illustrates how security principals correspond to roles:



10.3.1. Permissions

Authorization roles have different permissions with varying levels of access to Infinispan. Permissions let you restrict user access to both Cache Managers and caches.

Cache Manager permissions

Permission	Function	Description
CONFIGURATION	<code>defineConfiguration</code>	Defines new cache configurations.
LISTEN	<code>addListener</code>	Registers listeners against a Cache Manager.
LIFECYCLE	<code>stop</code>	Stops the Cache Manager.
CREATE	<code>createCache</code> , <code>removeCache</code>	Create and remove container resources such as caches, counters, schemas, and scripts.
MONITOR	<code>getStats</code>	Allows access to JMX statistics and the <code>metrics</code> endpoint.
ALL	-	Includes all Cache Manager permissions.

Cache permissions

Permission	Function	Description
READ	<code>get</code> , <code>contains</code>	Retrieves entries from a cache.
WRITE	<code>put</code> , <code>putIfAbsent</code> , <code>replace</code> , <code>remove</code> , <code>evict</code>	Writes, replaces, removes, evicts data in a cache.

Permission	Function	Description
EXEC	<code>distexec, streams</code>	Allows code execution against a cache.
LISTEN	<code>addListener</code>	Registers listeners against a cache.
BULK_READ	<code>keySet, values, entrySet, query</code>	Executes bulk retrieve operations.
BULK_WRITE	<code>clear, putAll</code>	Executes bulk write operations.
LIFECYCLE	<code>start, stop</code>	Starts and stops a cache.
ADMIN	<code>getVersion, addInterceptor*, removeInterceptor, getInterceptorChain, getEvictionManager, getComponentRegistry, getDistributionManager, getAuthorizationManager, evict, getRpcManager, getCacheConfiguration, getCacheManager, getInvocationContextContainer, setAvailability, getDataContainer, getStats, getXAResource</code>	Allows access to underlying components and internal structures.
MONITOR	<code>getStats</code>	Allows access to JMX statistics and the <code>metrics</code> endpoint.
ALL	-	Includes all cache permissions.
ALL_READ	-	Combines the READ and BULK_READ permissions.
ALL_WRITE	-	Combines the WRITE and BULK_WRITE permissions.

Reference

- [Infinispan Security API](#)

10.3.2. Role Mappers

Infinispan includes a `PrincipalRoleMapper` API that maps security Principals in a Subject to authorization roles that you can assign to users.

Cluster role mappers

`ClusterRoleMapper` uses a persistent replicated cache to dynamically store principal-to-role mappings for the default roles and permissions.

By default uses the Principal name as the role name and implements `org.infinispan.security.MutableRoleMapper` which exposes methods to change role mappings at runtime.

- Java class: `org.infinispan.security.mappers.ClusterRoleMapper`
- Declarative configuration: `<cluster-role-mapper />`

Identity role mappers

`IdentityRoleMapper` uses the Principal name as the role name.

- Java class: `org.infinispan.security.mappers.IdentityRoleMapper`
- Declarative configuration: `<identity-role-mapper />`

CommonName role mappers

`CommonNameRoleMapper` uses the Common Name (CN) as the role name if the Principal name is a Distinguished Name (DN).

For example this DN, `cn=managers,ou=people,dc=example,dc=com`, maps to the `managers` role.

- Java class: `org.infinispan.security.mappers.CommonRoleMapper`
- Declarative configuration: `<common-name-role-mapper />`

Custom role mappers

Custom role mappers are implementations of `org.infinispan.security.PrincipalRoleMapper`.

- Declarative configuration: `<custom-role-mapper class="my.custom.RoleMapper" />`

Reference

- [Infinispan Security API](#)
- [org.infinispan.security.PrincipalRoleMapper](#)

10.4. Access Control List (ACL) Cache

Infinispan caches roles that you grant to users internally for optimal performance. Whenever you grant or deny roles to users, Infinispan flushes the ACL cache to ensure user permissions are applied correctly.

If necessary, you can disable the ACL cache or configure it with the `cache-size` and `cache-timeout` attributes.

```
<security cache-size="1000" cache-timeout="300000">
  <authorization />
</security>
```

Reference

- [Infinispan configuration schema reference](#)

10.5. Customizing Roles and Permissions

You can customize authorization settings in your Infinispan configuration to use role mappers with different combinations of roles and permissions.

Procedure

1. Open your `infinispan.xml` configuration for editing.
2. Configure authorization for the `cache-container` by declaring a role mapper and a set of roles and permissions.
3. Configure authorization for caches to restrict access based on user roles.

The following configuration example shows how to configure security authorization with roles and permissions:

```
<infinispan>
  <cache-container default-cache="restricted" name="custom-authorization">
    <security>
      <authorization>
        <!-- Declare a role mapper that associates a security principal
             to each role. -->
        <identity-role-mapper />
        <!-- Specify user roles and corresponding permissions. -->
        <role name="admin" permissions="ALL" />
        <role name="reader" permissions="READ" />
        <role name="writer" permissions="WRITE" />
        <role name="supervisor" permissions="READ WRITE EXEC"/>
      </authorization>
    </security>
    <local-cache name="implicit-authorization">
      <security>
        <!-- Inherit roles and permissions from the cache-container. -->
        <authorization/>
      </security>
    </local-cache>
    <local-cache name="restricted">
      <security>
        <!-- Explicitly define which roles can access the cache. -->
        <authorization roles="admin supervisor"/>
      </security>
    </local-cache>
  </cache-container>
</infinispan>
```

10.6. Disabling Security Authorization

In local development environments you can disable authorization so that users do not need roles and permissions. Disabling security authorization means that any user can access data and interact with Infinispan resources.

Procedure

1. Open your `infinispan.xml` configuration for editing.
2. Remove any `authorization` elements from the `security` configuration for the `cache-container` and each cache configuration.

10.7. Configuring Authorization with Client Certificates

Enabling client certificate authentication means you do not need to specify Infinispan user credentials in client configuration, which means you must associate roles with the Common Name (CN) field in the client certificate(s).

Prerequisites

- Provide clients with a Java keystore that contains either their public certificates or part of the certificate chain, typically a public CA certificate.
- Configure Infinispan Server to perform client certificate authentication.

Procedure

1. Enable the `common-name-role-mapper` in the security authorization configuration.
2. Assign the Common Name (CN) from the client certificate a role with the appropriate permissions.

```
<cache-container name="certificate-authentication" statistics="true">
  <security>
    <authorization>
      <!-- Declare a role mapper that associates the common name (CN) field
           in client certificate trust stores with authorization roles. -->
      <common-name-role-mapper/>
      <!-- In this example, if a client certificate contains `CN=Client1` then
           clients with matching certificates get ALL permissions. -->
      <role name="Client1" permissions="ALL"/>
    </authorization>
  </security>
</cache-container>
```

Chapter 11. Setting up Infinispan cluster transport

Infinispan requires a transport layer so nodes can automatically join and leave clusters. The transport layer also enables Infinispan nodes to replicate or distribute data across the network and perform operations such as re-balancing and state transfer.

11.1. Default JGroups stacks

Infinispan provides default JGroups stack files, `default-jgroups-*.xml`, in the `default-configs` directory inside the `infinispan-core-13.0.4.Final.jar` file.

You can find this JAR file in the `$ISPN_HOME/lib` directory.

File name	Stack name	Description
<code>default-jgroups-udp.xml</code>	<code>udp</code>	Uses UDP for transport and UDP multicast for discovery. Suitable for larger clusters (over 100 nodes) or if you are using replicated caches or invalidation mode. Minimizes the number of open sockets.
<code>default-jgroups-tcp.xml</code>	<code>tcp</code>	Uses TCP for transport and the <code>MPING</code> protocol for discovery, which uses <code>UDP</code> multicast. Suitable for smaller clusters (under 100 nodes) <i>only if</i> you are using distributed caches because TCP is more efficient than UDP as a point-to-point protocol.
<code>default-jgroups-kubernetes.xml</code>	<code>kubernetes</code>	Uses TCP for transport and <code>DNS_PING</code> for discovery. Suitable for Kubernetes and Red Hat OpenShift nodes where UDP multicast is not always available.
<code>default-jgroups-ec2.xml</code>	<code>ec2</code>	Uses TCP for transport and <code>NATIVE_S3_PING</code> for discovery. Suitable for Amazon EC2 nodes where UDP multicast is not available. Requires additional dependencies.
<code>default-jgroups-google.xml</code>	<code>google</code>	Uses TCP for transport and <code>GOOGLE_PING2</code> for discovery. Suitable for Google Cloud Platform nodes where UDP multicast is not available. Requires additional dependencies.
<code>default-jgroups-azure.xml</code>	<code>azure</code>	Uses TCP for transport and <code>AZURE_PING</code> for discovery. Suitable for Microsoft Azure nodes where UDP multicast is not available. Requires additional dependencies.

Additional resources

- [JGroups Protocols](#)

11.2. Cluster discovery protocols

Infinispan supports different protocols that allow nodes to automatically find each other on the network and form clusters.

There are two types of discovery mechanisms that Infinispan can use:

- Generic discovery protocols that work on most networks and do not rely on external services.
- Discovery protocols that rely on external services to store and retrieve topology information for Infinispan clusters.

For instance the DNS_PING protocol performs discovery through DNS server records.



Running Infinispan on hosted platforms requires using discovery mechanisms that are adapted to network constraints that individual cloud providers impose.

Additional resources

- [JGroups Discovery Protocols](#)

11.2.1. PING

PING, or UDPPING is a generic JGroups discovery mechanism that uses dynamic multicasting with the UDP protocol.

When joining, nodes send PING requests to an IP multicast address to discover other nodes already in the Infinispan cluster. Each node responds to the PING request with a packet that contains the address of the coordinator node and its own address. C=coordinator's address and A=own address. If no nodes respond to the PING request, the joining node becomes the coordinator node in a new cluster.

PING configuration example

```
<PING num_discovery_runs="3"/>
```

Additional resources

- [JGroups PING](#)

11.2.2. TCPPING

TCPPING is a generic JGroups discovery mechanism that uses a list of static addresses for cluster members.

With TCPPING, you manually specify the IP address or hostname of each node in the Infinispan cluster as part of the JGroups stack, rather than letting nodes discover each other dynamically.

TCPPING configuration example

```
<TCP bind_port="7800" />
<TCPPING timeout="3000"
  initial_hosts="${jgroups.tcpping.initial_hosts:hostname1[port1],hostname2[port2]}"
  port_range="0"
  num_initial_members="3"/>
```

Additional resources

- [JGroups TCPPING](#)

11.2.3. MPING

MPING uses IP multicast to discover the initial membership of Infinispan clusters.

You can use MPING to replace TCPPING discovery with TCP stacks and use multicasting for discovery instead of static lists of initial hosts. However, you can also use MPING with UDP stacks.

MPING configuration example

```
<MPING mcast_addr="${jgroups.mcast_addr:228.6.7.8}"
  mcast_port="${jgroups.mcast_port:46655}"
  num_discovery_runs="3"
  ip_ttl="${jgroups.udp.ip_ttl:2}"/>
```

Additional resources

- [JGroups MPING](#)

11.2.4. TCPGOSSIP

Gossip routers provide a centralized location on the network from which your Infinispan cluster can retrieve addresses of other nodes.

You inject the address (**IP:PORT**) of the Gossip router into Infinispan nodes as follows:

1. Pass the address as a system property to the JVM; for example, `-DGossipRouterAddress="10.10.2.4[12001]"`.
2. Reference that system property in the JGroups configuration file.

Gossip router configuration example

```
<TCP bind_port="7800" />
<TCPGOSSIP timeout="3000"
  initial_hosts="${GossipRouterAddress}"
  num_initial_members="3" />
```

Additional resources

- [JGroups Gossip Router](#)

11.2.5. JDBC_PING

JDBC_PING uses shared databases to store information about Infinispan clusters. This protocol supports any database that can use a JDBC connection.

Nodes write their IP addresses to the shared database so joining nodes can find the Infinispan cluster on the network. When nodes leave Infinispan clusters, they delete their IP addresses from the shared database.

JDBC_PING configuration example

```
<JDBC_PING connection_url="jdbc:mysql://localhost:3306/database_name"
  connection_username="user"
  connection_password="password"
  connection_driver="com.mysql.jdbc.Driver"/>
```



Add the appropriate JDBC driver to the classpath so Infinispan can use JDBC_PING.

Additional resources

- [JDBC_PING](#)
- [JDBC_PING Wiki](#)

11.2.6. DNS_PING

JGroups DNS_PING queries DNS servers to discover Infinispan cluster members in Kubernetes environments such as OKD and Red Hat OpenShift.

DNS_PING configuration example

```
<dns.DNS_PING dns_query="myservice.myproject.svc.cluster.local" />
```

Additional resources

- [JGroups DNS_PING](#)
- [DNS for Services and Pods](#) (Kubernetes documentation for adding DNS entries)

11.2.7. Cloud discovery protocols

Infinispan includes default JGroups stacks that use discovery protocol implementations that are specific to cloud providers.

Discovery protocol	Default stack file	Artifact	Version
NATIVE_S3_PING	default-jgroups-ec2.xml	org.jgroups.aws.s3:native-s3-ping	1.0.0.Final

Discovery protocol	Default stack file	Artifact	Version
GOOGLE_PING2	default-jgroups-google.xml	org.jgroups.google:jgroups-google	1.0.0.Final
AZURE_PING	default-jgroups-azure.xml	org.jgroups.azure:jgroups-azure	1.3.0.Final

Providing dependencies for cloud discovery protocols

To use `NATIVE_S3_PING`, `GOOGLE_PING2`, or `AZURE_PING` cloud discovery protocols, you need to provide dependent libraries to Infinispan.

Procedure

1. Download the artifact JAR file and all dependencies.
2. Add the artifact JAR file and all dependencies to the `$ISPN_HOME/server/lib` directory of your Infinispan Server installation.

For more details see the [Downloading artifacts for JGroups cloud discover protocols for Data Grid Server](#) ({RedHat} knowledgebase article)

You can then configure the cloud discovery protocol as part of a JGroups stack file or with system properties.

Additional resources

- [JGroups NATIVE_S3_PING](#)
- [JGroups GOOGLE_PING2](#)
- [JGroups AZURE_PING](#)

11.3. Using the default JGroups stacks

Infinispan uses JGroups protocol stacks so nodes can send each other messages on dedicated cluster channels.

Infinispan provides preconfigured JGroups stacks for `UDP` and `TCP` protocols. You can use these default stacks as a starting point for building custom cluster transport configuration that is optimized for your network requirements.

Procedure

Do one of the following to use one of the default JGroups stacks:

- Use the `stack` attribute in your `infinispan.xml` file.

```
<infinispan>
  <cache-container default-cache="replicatedCache">
    <!-- Use the default UDP stack for cluster transport. -->
    <transport cluster="${infinispan.cluster.name}"
              stack="udp"
              node-name="${infinispan.node.name:}"/>
  </cache-container>
</infinispan>
```

- Use the `cluster-stack` argument to set the JGroups stack file when Infinispan Server starts:

```
$ bin/server.sh --cluster-stack=udp
```

Verification

Infinispan logs the following message to indicate which stack it uses:

```
[org.infinispan.CLUSTER] ISPN000078: Starting JGroups channel cluster with stack udp
```

11.4. Customizing JGroups stacks

Adjust and tune properties to create a cluster transport configuration that works for your network requirements.

Infinispan provides attributes that let you extend the default JGroups stacks for easier configuration. You can inherit properties from the default stacks while combining, removing, and replacing other properties.

Procedure

1. Create a new JGroups stack declaration in your `infinispan.xml` file.
2. Add the `extends` attribute and specify a JGroups stack to inherit properties from.
3. Use the `stack.combine` attribute to modify properties for protocols configured in the inherited stack.
4. Use the `stack.position` attribute to define the location for your custom stack.
5. Specify the stack name as the value for the `stack` attribute in the `transport` configuration.

For example, you might evaluate using a Gossip router and symmetric encryption with the default TCP stack as follows:

```

<infinispan>
  <jgroups>
    <!-- Creates a custom JGroups stack named "my-stack". -->
    <!-- Inherits properties from the default TCP stack. -->
    <stack name="my-stack" extends="tcp">
      <!-- Uses TCPGOSSIP as the discovery mechanism instead of MPING -->
      <TCPGOSSIP initial_hosts=
"`${jgroups.tunnel.gossip_router_hosts:localhost[12001]}`"
        stack.combine="REPLACE"
        stack.position="MPING" />
      <!-- Removes the FD_SOCKET protocol from the stack. -->
      <FD_SOCKET stack.combine="REMOVE"/>
      <!-- Modifies the timeout value for the VERIFY_SUSPECT protocol. -->
      <VERIFY_SUSPECT timeout="2000"/>
      <!-- Adds SYM_ENCRYPT to the stack after VERIFY_SUSPECT. -->
      <SYM_ENCRYPT sym_algorithm="AES"
        keystore_name="mykeystore.p12"
        keystore_type="PKCS12"
        store_password="changeit"
        key_password="changeit"
        alias="myKey"
        stack.combine="INSERT_AFTER"
        stack.position="VERIFY_SUSPECT" />
    </stack>
    <cache-container name="default" statistics="true">
      <!-- Uses "my-stack" for cluster transport. -->
      <transport cluster="`${infinispan.cluster.name}`"
        stack="my-stack"
        node-name="`${infinispan.node.name:}`"/>
    </cache-container>
  </jgroups>
</infinispan>

```

6. Check Infinispan logs to ensure it uses the stack.

```
[org.infinispan.CLUSTER] ISPN000078: Starting JGroups channel cluster with stack my-stack
```

11.4.1. Inheritance attributes

When you extend a JGroups stack, inheritance attributes let you adjust protocols and properties in the stack you are extending.

- `stack.position` specifies protocols to modify.
- `stack.combine` uses the following values to extend JGroups stacks:

Value	Description
COMBINE	Overrides protocol properties.
REPLACE	Replaces protocols.
INSERT_AFTER	<p>Adds a protocol into the stack after another protocol. Does not affect the protocol that you specify as the insertion point.</p> <p>Protocols in JGroups stacks affect each other based on their location in the stack. For example, you should put a protocol such as <code>NAKACK2</code> after the <code>SYM_ENCRYPT</code> or <code>ASYM_ENCRYPT</code> protocol so that <code>NAKACK2</code> is secured.</p>
INSERT_BEFORE	<p>Inserts a protocols into the stack before another protocol. Affects the protocol that you specify as the insertion point.</p>
REMOVE	Removes protocols from the stack.

11.5. Using JGroups system properties

Pass system properties to Infinispan at startup to tune cluster transport.

Procedure

- Use `-D<property-name>=<property-value>` arguments to set JGroups system properties as required.

For example, set a custom bind port and IP address as follows:

```
$ bin/server.sh -Djgroups.bind.port=1234 -Djgroups.bind.address=192.0.2.0
```

11.5.1. Cluster transport properties

Use the following properties to customize JGroups cluster transport.

System Property	Description	Default Value	Required/Optional
<code>jgroups.bind.address</code>	Bind address for cluster transport.	<code>SITE_LOCAL</code>	Optional
<code>jgroups.bind.port</code>	Bind port for the socket.	<code>7800</code>	Optional
<code>jgroups.mcast_addr</code>	IP address for multicast, both discovery and inter-cluster communication. The IP address must be a valid "class D" address that is suitable for IP multicast.	<code>228.6.7.8</code>	Optional
<code>jgroups.mcast_port</code>	Port for the multicast socket.	<code>46655</code>	Optional

System Property	Description	Default Value	Required/Optional
<code>jgroups.ip_ttl</code>	Time-to-live (TTL) for IP multicast packets. The value defines the number of network hops a packet can make before it is dropped.	2	Optional
<code>jgroups.thread_pool.min_threads</code>	Minimum number of threads for the thread pool.	0	Optional
<code>jgroups.thread_pool.max_threads</code>	Maximum number of threads for the thread pool.	200	Optional
<code>jgroups.join_timeout</code>	Maximum number of milliseconds to wait for join requests to succeed.	2000	Optional
<code>jgroups.thread_dumps_threshold</code>	Number of times a thread pool needs to be full before a thread dump is logged.	10000	Optional

Additional resources

- [JGroups system properties](#)
- [JGroups protocol list](#)

11.5.2. System properties for cloud discovery protocols

Use the following properties to configure JGroups discovery protocols for hosted platforms.

Amazon EC2

System properties for configuring `NATIVE_S3_PING`.

System Property	Description	Default Value	Required/Optional
<code>jgroups.s3.region_name</code>	Name of the Amazon S3 region.	No default value.	Optional
<code>jgroups.s3.bucket_name</code>	Name of the Amazon S3 bucket. The name must exist and be unique.	No default value.	Optional

Google Cloud Platform

System properties for configuring `GOOGLE_PING2`.

System Property	Description	Default Value	Required/Optional
<code>jgroups.google.bucket_name</code>	Name of the Google Compute Engine bucket. The name must exist and be unique.	No default value.	Required

Azure

System properties for `AZURE_PING`.

System Property	Description	Default Value	Required/Optional
<code>jboss.jgroups.azure_ping.storage_account_name</code>	Name of the Azure storage account. The name must exist and be unique.	No default value.	Required
<code>jboss.jgroups.azure_ping.storage_access_key</code>	Name of the Azure storage access key.	No default value.	Required
<code>jboss.jgroups.azure_ping.container</code>	Valid DNS name of the container that stores ping information.	No default value.	Required

Kubernetes

System properties for `DNS_PING`.

System Property	Description	Default Value	Required/Optional
<code>jgroups.dns.query</code>	Sets the DNS record that returns cluster members.	No default value.	Required

11.6. Using inline JGroups stacks

You can insert complete JGroups stack definitions into `infinispan.xml` files.

Procedure

- Embed a custom JGroups stack declaration in your `infinispan.xml` file.

```

<infinispan>
  <!-- Contains one or more JGroups stack definitions. -->
  <jgroups>
    <!-- Defines a custom JGroups stack named "prod". -->
    <stack name="prod">
      <TCP bind_port="7800" port_range="30" recv_buf_size="20000000" send_buf_size
="640000"/>
      <MPING break_on_coord_rsp="true"
mcast_addr="${jgroups.mping.mcast_addr:228.2.4.6}"
mcast_port="${jgroups.mping.mcast_port:43366}"
num_discovery_runs="3"
ip_ttl="${jgroups.udp.ip_ttl:2}"/>
      <MERGE3 />
      <FD_SOCK />
      <FD_ALL timeout="3000" interval="1000" timeout_check_interval="1000" />
      <VERIFY_SUSPECT timeout="1000" />
      <pbcast.NAKACK2 use_mcast_xmit="false" xmit_interval="100"
xmit_table_num_rows="50"
xmit_table_msgs_per_row="1024"
xmit_table_max_compaction_time="30000" />
      <UNICAST3 xmit_interval="100" xmit_table_num_rows="50"
xmit_table_msgs_per_row="1024"
xmit_table_max_compaction_time="30000" />
      <pbcast.STABLE desired_avg_gossip="2000" max_bytes="1M" />
      <pbcast.GMS print_local_addr="false" join_timeout=
"${jgroups.join_timeout:2000}" />
      <UFC max_credits="4m" min_threshold="0.40" />
      <MFC max_credits="4m" min_threshold="0.40" />
      <FRAG3 />
    </stack>
  </jgroups>
  <cache-container default-cache="replicatedCache">
    <!-- Uses "prod" for cluster transport. -->
    <transport cluster="${infinispan.cluster.name}"
stack="prod"
node-name="${infinispan.node.name:}"/>
  </cache-container>
</infinispan>

```

11.7. Using external JGroups stacks

Reference external files that define custom JGroups stacks in `infinispan.xml` files.

Procedure

1. Add custom JGroups stack files to the `$ISPN_HOME/server/conf` directory.

Alternatively you can specify an absolute path when you declare the external stack file.

2. Reference the external stack file with the `stack-file` element.

```

<infinispan>
  <jgroups>
    <!-- Creates a "prod-tcp" stack that references an external file. -->
    <stack-file name="prod-tcp" path="prod-jgroups-tcp.xml"/>
  </jgroups>
  <cache-container default-cache="replicatedCache">
    <!-- Use the "prod-tcp" stack for cluster transport. -->
    <transport stack="prod-tcp" />
    <replicated-cache name="replicatedCache"/>
  </cache-container>
  <!-- Cache configuration goes here. -->
</infinispan>

```

11.8. Encrypting cluster transport

Secure cluster transport so that nodes communicate with encrypted messages. You can also configure Infinispan clusters to perform certificate authentication so that only nodes with valid identities can join.

11.8.1. Securing cluster transport with TLS identities

Add SSL/TLS identities to a Infinispan Server security realm and use them to secure cluster transport. Nodes in the Infinispan Server cluster then exchange SSL/TLS certificates to encrypt JGroups messages, including RELAY messages if you configure cross-site replication.

Prerequisites

- Install a Infinispan Server cluster.

Procedure

1. Create a TLS keystore that contains a single certificate to identify Infinispan Server.

You can also use a PEM file if it contains a private key in PKCS#1 or PKCS#8 format, a certificate, and has an empty password: `password=""`.



If the certificate in the keystore is not signed by a public certificate authority (CA) then you must also create a trust store that contains either the signing certificate or the public key.

2. Add the keystore to the `$ISPN_HOME/server/conf` directory.
3. Add the keystore to a new security realm in your Infinispan Server configuration.



You should create dedicated keystores and security realms so that Infinispan Server endpoints do not use the same security realm as cluster transport.


```

<security xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
  xsi:schemaLocation="urn:infinispan:server:13.0
https://infinispan.org/schemas/infinispan-server-13.0.xsd"
  xmlns="urn:infinispan:server:13.0">
  <security-realms>
    <security-realm name="cluster-transport">
      <server-identities>
        <ssl>
          <!-- Adds a keystore that contains a certificate that provides
                SSL/TLS identity to encrypt cluster transport. -->
          <keystore path="server.pfx"
            relative-to="infinispan.server.config.path"
            password="secret"
            alias="server"/>
        </ssl>
      </server-identities>
    </security-realm>
  </security-realms>
</security>

```

4. Configure cluster transport to use the security realm by specifying the name of the security realm with the `server:security-realm` attribute.

```

<cache-container>
  <transport server:security-realm="cluster-transport"/>
</cache-container>

```

Verification

When you start Infinispan Server, the following log message indicates that the cluster is using the security realm for cluster transport:

```
[org.infinispan.SERVER] ISPN080060: SSL Transport using realm <security_realm_name>
```

11.8.2. JGroups encryption protocols

To secure cluster traffic, you can configure Infinispan nodes to encrypt JGroups message payloads with secret keys.

Infinispan nodes can obtain secret keys from either:

- The coordinator node (asymmetric encryption).
- A shared keystore (symmetric encryption).

Retrieving secret keys from coordinator nodes

You configure asymmetric encryption by adding the `ASYM_ENCRYPT` protocol to a JGroups stack in your Infinispan configuration. This allows Infinispan clusters to generate and distribute secret keys.



When using asymmetric encryption, you should also provide keystores so that nodes can perform certificate authentication and securely exchange secret keys. This protects your cluster from man-in-the-middle (MitM) attacks.

Asymmetric encryption secures cluster traffic as follows:

1. The first node in the Infinispan cluster, the coordinator node, generates a secret key.
2. A joining node performs certificate authentication with the coordinator to mutually verify identity.
3. The joining node requests the secret key from the coordinator node. That request includes the public key for the joining node.
4. The coordinator node encrypts the secret key with the public key and returns it to the joining node.
5. The joining node decrypts and installs the secret key.
6. The node joins the cluster, encrypting and decrypting messages with the secret key.

Retrieving secret keys from shared keystores

You configure symmetric encryption by adding the `SYM_ENCRYPT` protocol to a JGroups stack in your Infinispan configuration. This allows Infinispan clusters to obtain secret keys from keystores that you provide.

1. Nodes install the secret key from a keystore on the Infinispan classpath at startup.
2. Node join clusters, encrypting and decrypting messages with the secret key.

Comparison of asymmetric and symmetric encryption

`ASYM_ENCRYPT` with certificate authentication provides an additional layer of encryption in comparison with `SYM_ENCRYPT`. You provide keystores that encrypt the requests to coordinator nodes for the secret key. Infinispan automatically generates that secret key and handles cluster traffic, while letting you specify when to generate secret keys. For example, you can configure clusters to generate new secret keys when nodes leave. This ensures that nodes cannot bypass certificate authentication and join with old keys.

`SYM_ENCRYPT`, on the other hand, is faster than `ASYM_ENCRYPT` because nodes do not need to exchange keys with the cluster coordinator. A potential drawback to `SYM_ENCRYPT` is that there is no configuration to automatically generate new secret keys when cluster membership changes. Users are responsible for generating and distributing the secret keys that nodes use to encrypt cluster traffic.

11.8.3. Securing cluster transport with asymmetric encryption

Configure Infinispan clusters to generate and distribute secret keys that encrypt JGroups messages.

Procedure

1. Create a keystore with certificate chains that enables Infinispan to verify node identity.
2. Place the keystore on the classpath for each node in the cluster.

For Infinispan Server, you put the keystore in the \$ISPN_HOME directory.

3. Add the `SSL_KEY_EXCHANGE` and `ASYM_ENCRYPT` protocols to a JGroups stack in your Infinispan configuration, as in the following example:

```
<infinispan>
  <jgroups>
    <!-- Creates a secure JGroups stack named "encrypt-tcp" that extends the
    default TCP stack. -->
    <stack name="encrypt-tcp" extends="tcp">
      <!-- Adds a keystore that nodes use to perform certificate authentication.
      -->
      <!-- Uses the stack.combine and stack.position attributes to insert
      SSL_KEY_EXCHANGE into the default TCP stack after VERIFY_SUSPECT. -->
      <SSL_KEY_EXCHANGE keystore_name="mykeystore.jks"
        keystore_password="changeit"
        stack.combine="INSERT_AFTER"
        stack.position="VERIFY_SUSPECT"/>
      <!-- Configures ASYM_ENCRYPT -->
      <!-- Uses the stack.combine and stack.position attributes to insert
      ASYM_ENCRYPT into the default TCP stack before pbcast.NAKACK2. -->
      <!-- The use_external_key_exchange = "true" attribute configures nodes to use
      the 'SSL_KEY_EXCHANGE' protocol for certificate authentication. -->
      <ASYM_ENCRYPT asym_keylength="2048"
        asym_algorithm="RSA"
        change_key_on_coord_leave = "false"
        change_key_on_leave = "false"
        use_external_key_exchange = "true"
        stack.combine="INSERT_BEFORE"
        stack.position="pbcast.NAKACK2"/>
    </stack>
  </jgroups>
  <cache-container name="default" statistics="true">
    <!-- Configures the cluster to use the JGroups stack. -->
    <transport cluster="${infinispan.cluster.name}"
      stack="encrypt-tcp"
      node-name="${infinispan.node.name:}"/>
  </cache-container>
</infinispan>
```

Verification

When you start your Infinispan cluster, the following log message indicates that the cluster is using the secure JGroups stack:

```
[org.infinispan.CLUSTER] ISPN000078: Starting JGroups channel cluster with stack
<encrypted_stack_name>
```

Infinispan nodes can join the cluster only if they use `ASYM_ENCRYPT` and can obtain the secret key

from the coordinator node. Otherwise the following message is written to Infinispan logs:

```
[org.jgroups.protocols.ASYM_ENCRYPT] <hostname>: received message without encrypt header from <hostname>; dropping it
```

Additional resources

- [JGroups 4 Manual](#)
- [JGroups 4.2 Schema](#)

11.8.4. Securing cluster transport with symmetric encryption

Configure Infinispan clusters to encrypt JGroups messages with secret keys from keystores that you provide.

Procedure

1. Create a keystore that contains a secret key.
2. Place the keystore on the classpath for each node in the cluster.

For Infinispan Server, you put the keystore in the `$ISPN_HOME` directory.

3. Add the `SYM_ENCRYPT` protocol to a JGroups stack in your Infinispan configuration.

```
<infinispan>
  <jgroups>
    <!-- Creates a secure JGroups stack named "encrypt-tcp" that extends the default
    TCP stack. -->
    <stack name="encrypt-tcp" extends="tcp">
      <!-- Adds a keystore from which nodes obtain secret keys. -->
      <!-- Uses the stack.combine and stack.position attributes to insert SYM_ENCRYPT
      into the default TCP stack after VERIFY_SUSPECT. -->
      <SYM_ENCRYPT keystore_name="myKeystore.p12"
        keystore_type="PKCS12"
        store_password="changeit"
        key_password="changeit"
        alias="myKey"
        stack.combine="INSERT_AFTER"
        stack.position="VERIFY_SUSPECT"/>
    </stack>
  </jgroups>
  <cache-container name="default" statistics="true">
    <!-- Configures the cluster to use the JGroups stack. -->
    <transport cluster="{infinispan.cluster.name}"
      stack="encrypt-tcp"
      node-name="{infinispan.node.name:}"/>
  </cache-container>
</infinispan>
```

Verification

When you start your Infinispan cluster, the following log message indicates that the cluster is using the secure JGroups stack:

```
[org.infinispan.CLUSTER] ISPN000078: Starting JGroups channel cluster with stack <encrypted_stack_name>
```

Infinispan nodes can join the cluster only if they use `SYM_ENCRYPT` and can obtain the secret key from the shared keystore. Otherwise the following message is written to Infinispan logs:

```
[org.jgroups.protocols.SYM_ENCRYPT] <hostname>: received message without encrypt header from <hostname>; dropping it
```

Additional resources

- [JGroups 4 Manual](#)
- [JGroups 4.2 Schema](#)

11.9. TCP and UDP ports for cluster traffic

Infinispan uses the following ports for cluster transport messages:

Default Port	Protocol	Description
7800	TCP/UDP	JGroups cluster bind port
46655	UDP	JGroups multicast

Cross-site replication

Infinispan uses the following ports for the JGroups RELAY2 protocol:

7900

For Infinispan clusters running on Kubernetes.

7800

If using UDP for traffic between nodes and TCP for traffic between clusters.

7801

If using TCP for traffic between nodes and TCP for traffic between clusters.

Chapter 12. Configuring Infinispan Server with managed datasources

Add managed datasources to Infinispan Server configuration and optimize connection pooling and performance for JDBC database connections.

12.1. Configuring Infinispan Server with managed datasources

Create managed datasources as part of your Infinispan Server configuration to optimize connection pooling and performance for JDBC database connections. You can then use these datasources as part of your JDBC cache store configuration.

Prerequisites

- Copy database drivers to the `server/lib` directory in your Infinispan Server installation.



Use the `install` command with the Infinispan Command Line Interface (CLI) to download the required drivers to the `server/lib` directory, for example:

```
install org.postgresql:postgresql:42.1.3
```

Procedure

1. Open your Infinispan Server configuration for editing.
2. Add a new `data-source` to the `data-sources` section.
3. Uniquely identify the datasource with the `name` attribute or field.
4. Specify a JNDI name for the datasource with the `jndi-name` attribute or field.



You use the JNDI name to specify the datasource in your JDBC cache store configuration.

5. Set `true` as the value of the `statistics` attribute or field to enable statistics for the datasource through the `/metrics` endpoint.
6. Provide JDBC driver details that define how to connect to the datasource in the `connection-factory` section.
 - a. Specify the name of the database driver with the `driver` attribute or field.
 - b. Specify the JDBC connection url with the `url` attribute or field.
 - c. Specify credentials with the `username` and `password` attributes or fields.
 - d. Provide any other configuration as appropriate.
7. Define how Infinispan Server nodes pool and reuse connections with connection pool tuning properties in the `connection-pool` section.

Verification

Use the Infinispan Command Line Interface (CLI) to test the datasource connection, as follows:

1. Start a CLI session.

```
$ bin/cli.sh
```

2. List all datasources and confirm the one you created is available.

```
[//containers/default]> server datasource ls
```

3. Test a datasource connection.

```
[//containers/default]> server datasource test my-datasource
```

Next steps

Now that you have created a managed datasource in your Infinispan Server configuration, you can reference the JNDI name in cache store configuration as in the following example:

```
<distributed-cache-configuration name="persistent-cache" xmlns:jdbc=
"urn:infinispan:config:store:jdbc:13.0">
  <persistence>
    <jdbc:string-keyed-jdbc-store>
      <!-- Specifies the JNDI name for the datasource connection
      in Infinispan Server configuration. -->
      <jdbc:data-source jndi-url="jdbc/postgres"/>
      <jdbc:string-keyed-table drop-on-exit="true"
        create-on-start="true"
        prefix="TBL">
        <jdbc:id-column name="ID" type="VARCHAR(255)"/>
        <jdbc:data-column name="DATA" type="BYTEA"/>
        <jdbc:timestamp-column name="TS" type="BIGINT"/>
        <jdbc:segment-column name="S" type="INT"/>
      </jdbc:string-keyed-table>
    </jdbc:string-keyed-jdbc-store>
  </persistence>
</distributed-cache-configuration>
```

12.2. Managed datasources for JDBC connections

Managed datasources centralize JDBC connection configuration for your Infinispan cluster and share connection pools for Infinispan Server nodes.

```
<data-sources>
  <!-- Defines a unique name for the datasource and JNDI name that you
        reference in JDBC cache store configuration.
        Enables statistics for the datasource, if required. -->
  <data-source name="ds"
              jndi-name="jdbc/postgres"
              statistics="true">
    <!-- Specifies the JDBC driver that creates connections. -->
    <connection-factory driver="org.postgresql.Driver"
                      url="jdbc:postgresql://localhost:5432/postgres"
                      username="postgres"
                      password="changeme">
      <!-- Sets optional JDBC driver-specific connection properties. -->
      <connection-property name="name">value</connection-property>
    </connection-factory>
    <!-- Defines connection pool tuning properties. -->
    <connection-pool initial-size="1"
                    max-size="10"
                    min-size="3"
                    background-validation="1000"
                    idle-removal="1"
                    blocking-timeout="1000"
                    leak-detection="10000"/>
  </data-source>
</data-sources>
```



```
{
  "data-sources": [
    {
      "name": "ds",
      "jndi-name": "jdbc/postgres",
      "statistics": true,
      "connection-factory": {
        "driver": "org.postgresql.Driver",
        "url": "jdbc:postgresql://localhost:5432/postgres",
        "username": "postgres",
        "password": "changeme",
        "connection-properties": {
          "name": "value"
        }
      },
      "connection-pool": {
        "initial-size": 1,
        "max-size": 10,
        "min-size": 3,
        "background-validation": 1000,
        "idle-removal": 1,
        "blocking-timeout": 1000,
        "leak-detection": 10000
      }
    }
  ]
}
```

```

data-sources:
- name: ds
  jndi-name: 'jdbc/postgres'
  statistics: true
  connection-factory:
    driver: "org.postgresql.Driver"
    url: "jdbc:postgresql://localhost:5432/postgres"
    username: "postgres"
    password: "changeme"
    connection-properties:
      name: value
  connection-pool:
    initial-size: 1
    max-size: 10
    min-size: 3
    background-validation: 1000
    idle-removal: 1
    blocking-timeout: 1000
    leak-detection: 10000

```

Connection pool tuning properties

You can tune connection pools with the following parameters:

Parameter	Description
<code>initial-size</code>	Initial number of connections the pool should hold.
<code>max-size</code>	Maximum number of connections in the pool.
<code>min-size</code>	Minimum number of connections the pool should hold.
<code>blocking-timeout</code>	Maximum time in milliseconds to block while waiting for a connection before throwing an exception. This will never throw an exception if creating a new connection takes an inordinately long period of time. Default is <code>0</code> meaning that a call will wait indefinitely.
<code>background-validation</code>	Time in milliseconds between background validation runs. A duration of <code>0</code> means that this feature is disabled.
<code>validate-on-acquisition</code>	Connections idle for longer than this time, specified in milliseconds, are validated before being acquired (foreground validation). A duration of <code>0</code> means that this feature is disabled.
<code>idle-removal</code>	Time in minutes a connection has to be idle before it can be removed.
<code>leak-detection</code>	Time in milliseconds a connection has to be held before a leak warning.

Chapter 13. Remotely Executing Server-Side Tasks

Define and add tasks to Infinispan servers that you can invoke from the Infinispan command line interface, REST API, or from Hot Rod clients.

You can implement tasks as custom Java classes or define scripts in languages such as JavaScript.

13.1. Creating Server Tasks

Create custom task implementations and add them to Infinispan servers.

13.1.1. Server Tasks

Infinispan server tasks are classes that extend the `org.infinispan.tasks.ServerTask` interface and generally include the following method calls:

`setTaskContext()`

Allows access to execution context information including task parameters, cache references on which tasks are executed, and so on. In most cases, implementations store this information locally and use it when tasks are actually executed.

`getName()`

Returns unique names for tasks. Clients invoke tasks with these names.

`getExecutionMode()`

Returns the execution mode for tasks.

- `TaskExecutionMode.ONE_NODE` only the node that handles the request executes the script. Although scripts can still invoke clustered operations.
- `TaskExecutionMode.ALL_NODES` Infinispan uses clustered executors to run scripts across nodes. For example, server tasks that invoke stream processing need to be executed on a single node because stream processing is distributed to all nodes.

`call()`

Computes a result. This method is defined in the `java.util.concurrent.Callable` interface and is invoked with server tasks.



Server task implementations must adhere to service loader pattern requirements. For example, implementations must have a zero-argument constructors.

The following `HelloTask` class implementation provides an example task that has one parameter:

```

package example;

import org.infinispan.tasks.ServerTask;
import org.infinispan.tasks.TaskContext;

public class HelloTask implements ServerTask<String> {

    private TaskContext ctx;

    @Override
    public void setTaskContext(TaskContext ctx) {
        this.ctx = ctx;
    }

    @Override
    public String call() throws Exception {
        String name = (String) ctx.getParameters().get().get("name");
        return "Hello " + name;
    }

    @Override
    public String getName() {
        return "hello-task";
    }

}

```

Reference

- [org.infinispan.tasks.ServerTask](#)
- [java.util.concurrent.Callable.call\(\)](#)
- [java.util.ServiceLoader](#)

13.1.2. Deploying Server Tasks to Infinispan Servers

Add your custom server task classes to Infinispan servers.

Prerequisites

Stop any running Infinispan servers. Infinispan does not support runtime deployment of custom classes.

Procedure

1. Add a `META-INF/services/org.infinispan.tasks.ServerTask` file that contains the fully qualified names of server tasks, for example:

```
example.HelloTask
```

2. Package your server task implementation in a JAR file.

3. Copy the JAR file to the `$ISPAN_HOME/server/lib` directory of your Infinispan server.
4. Add your classes to the deserialization allow list in your Infinispan configuration. Alternatively set the allow list using system properties.

Reference

- [Adding Java Classes to Deserialization Allow Lists](#)
- [Infinispan 13.0 Configuration Schema](#)

13.2. Creating Server Scripts

Create custom scripts and add them to Infinispan servers.

13.2.1. Server Scripts

Infinispan server scripting is based on the `javax.script` API and is compatible with any JVM-based ScriptEngine implementation.

Hello World Script Example

The following is a simple example that runs on a single Infinispan server, has one parameter, and uses JavaScript:

```
// mode=local,language=javascript,parameters=[greetee]
"Hello " + greetee
```

When you run the preceding script, you pass a value for the `greetee` parameter and Infinispan returns `"Hello ${value}"`.

Script Metadata

Metadata provides additional information about scripts that Infinispan servers use when running scripts.

Script metadata are `property=value` pairs that you add to comments in the first lines of scripts, such as the following example:

```
// name=test, language=javascript
// mode=local, parameters=[a,b,c]
```

- Use comment styles that match the scripting language (`//`, `;;`, `#`).
- Separate `property=value` pairs with commas.
- Separate values with single (') or double (") quote characters.

Table 1. Metadata Properties

Property	Description
<code>mode</code>	<p>Defines the execution mode and has the following values:</p> <p><code>local</code> only the node that handles the request executes the script. Although scripts can still invoke clustered operations.</p> <p><code>distributed</code> Infinispan uses clustered executors to run scripts across nodes.</p>
<code>language</code>	Specifies the ScriptEngine that executes the script.
<code>extension</code>	Specifies filename extensions as an alternative method to set the ScriptEngine.
<code>role</code>	Specifies roles that users must have to execute scripts.
<code>parameters</code>	Specifies an array of valid parameter names for this script. Invocations which specify parameters not included in this list cause exceptions.
<code>datatype</code>	<p>Optionally sets the MediaType (MIME type) for storing data as well as parameter and return values. This property is useful for remote clients that support particular data formats only.</p> <p>Currently you can set only <code>text/plain;</code> <code>charset=utf-8</code> to use the String UTF-8 format for data.</p>

Script Bindings

Infinispan exposes internal objects as bindings for script execution.

Binding	Description
<code>cache</code>	Specifies the cache against which the script is run.
<code>marshaller</code>	Specifies the marshaller to use for serializing data to the cache.
<code>cacheManager</code>	Specifies the <code>cacheManager</code> for the cache.
<code>scriptingManager</code>	Specifies the instance of the script manager that runs the script. You can use this binding to run other scripts from a script.

Script Parameters

Infinispan lets you pass named parameters as bindings for running scripts.

Parameters are `name,value` pairs, where `name` is a string and `value` is any value that the marshaller can interpret.

The following example script has two parameters, `multiplicand` and `multiplier`. The script takes the value of `multiplicand` and multiplies it with the value of `multiplier`.

```
// mode=local,language=javascript
multiplicand * multiplier
```

When you run the preceding script, Infinispan responds with the result of the expression evaluation.

13.2.2. Adding Scripts to Infinispan Servers

Use the command line interface to add scripts to Infinispan servers.

Prerequisites

Infinispan Server stores scripts in the `__script_cache` cache. If you enable cache authorization, users must have `CREATE` permissions to add to `__script_cache`.

Assign users the `deployer` role at minimum if you use default authorization settings.

Procedure

1. Define scripts as required.

For example, create a file named `multiplication.js` that runs on a single Infinispan server, has two parameters, and uses JavaScript to multiply a given value:

```
// mode=local,language=javascript
multiplicand * multiplier
```

2. Create a CLI connection to Infinispan.
3. Use the `task` command to upload scripts, as in the following example:

```
[//containers/default]> task upload --file=multiplication.js multiplication
```

4. Verify that your scripts are available.

```
[//containers/default]> ls tasks
multiplication
```

13.2.3. Programmatically Creating Scripts

Add scripts with the Hot Rod `RemoteCache` interface as in the following example:

```
RemoteCache<String, String> scriptCache = cacheManager.getCache("__script_cache");
scriptCache.put("multiplication.js",
    "// mode=local,language=javascript\n" +
    "multiplicand * multiplier\n");
```

Reference

org.infinispan.client.hotrod.RemoteCache

13.3. Running Server-Side Tasks and Scripts

Execute tasks and custom scripts on Infinispan servers.

13.3.1. Running Tasks and Scripts

Use the command line interface to run tasks and scripts on Infinispan clusters.

Procedure

1. Create a CLI connection to Infinispan.
2. Use the `task` command to run tasks and scripts, as in the following examples:
 - Execute a script named `multiplier.js` and specify two parameters:

```
[//containers/default]> task exec multiplier.js -Pmultiplicand=10 -Pmultiplier=20
200.0
```

- Execute a task named `@@cache@names` to retrieve a list of all available caches:

```
//containers/default]> task exec @@cache@names
["__protobuf_metadata","mycache","__script_cache"]
```

13.3.2. Programmatically Running Scripts

Call the `execute()` method to run scripts with the Hot Rod `RemoteCache` interface, as in the following example:


```
RemoteCache<String, Integer> cache = cacheManager.getCache();
// Create parameters for script execution.
Map<String, Object> params = new HashMap<>();
params.put("multiplicand", 10);
params.put("multiplier", 20);
// Run the script with the parameters.
Object result = cache.execute("multiplication.js", params);
```

Reference

org.infinispan.client.hotrod.RemoteCache

13.3.3. Programmatically Running Tasks

Call the `execute()` method to run tasks with the Hot Rod `RemoteCache` interface, as in the following example:

```
// Add configuration for a locally running server.
ConfigurationBuilder builder = new ConfigurationBuilder();
builder.addServer().host("127.0.0.1").port(11222);

// Connect to the server.
RemoteCacheManager cacheManager = new RemoteCacheManager(builder.build());

// Retrieve the remote cache.
RemoteCache<String, String> cache = cacheManager.getCache();

// Create task parameters.
Map<String, String> parameters = new HashMap<>();
parameters.put("name", "developer");

// Run the server task.
String greet = cache.execute("hello-task", parameters);
System.out.println(greet);
```

Reference

org.infinispan.client.hotrod.RemoteCache

Chapter 14. Enabling and Customizing Logging

Infinispan uses Apache Log4j 2 to provide configurable logging mechanisms that capture details about the environment and record cache operations for troubleshooting purposes and root cause analysis.

14.1. Server Logs

Infinispan writes server logs to the following files in the `$ISPN_HOME/server/log` directory:

`server.log`

Messages in human readable format, including boot logs that relate to the server startup. Infinispan creates this file when you start the server.

`server.log.json`

Messages in JSON format that let you parse and analyze Infinispan logs. Infinispan creates this file when you enable the `JSON-FILE` appender.

14.1.1. Configuring Server Logs

Infinispan uses Apache Log4j technology to write server log messages. You can configure server logs in the `log4j2.xml` file.

Procedure

1. Open `$ISPN_HOME/server/conf/log4j2.xml` with any text editor.
2. Change server logging as appropriate.
3. Save and close `log4j2.xml`.

Additional resources

- [Apache Log4j manual](#)

14.1.2. Log Levels

Log levels indicate the nature and severity of messages.

Log level	Description
TRACE	Fine-grained debug messages, capturing the flow of individual requests through the application.
DEBUG	Messages for general debugging, not related to an individual request.
INFO	Messages about the overall progress of applications, including lifecycle events.

Log level	Description
WARN	Events that can lead to error or degrade performance.
ERROR	Error conditions that might prevent operations or activities from being successful but do not prevent applications from running.
FATAL	Events that could cause critical service failure and application shutdown.

In addition to the levels of individual messages presented above, the configuration allows two more values: **ALL** to include all messages, and **OFF** to exclude all messages.

14.1.3. Infinispan Log Categories

Infinispan provides categories for **INFO**, **WARN**, **ERROR**, **FATAL** level messages that organize logs by functional area.

org.infinispan.CLUSTER

Messages specific to Infinispan clustering that include state transfer operations, rebalancing events, partitioning, and so on.

org.infinispan.CONFIG

Messages specific to Infinispan configuration.

org.infinispan.CONTAINER

Messages specific to the data container that include expiration and eviction operations, cache listener notifications, transactions, and so on.

org.infinispan.PERSISTENCE

Messages specific to cache loaders and stores.

org.infinispan.SECURITY

Messages specific to Infinispan security.

org.infinispan.SERVER

Messages specific to Infinispan servers.

org.infinispan.XSITE

Messages specific to cross-site replication operations.

14.1.4. Log Appenders

Log appenders define how Infinispan records log messages.

CONSOLE

Write log messages to the host standard out (**stdout**) or standard error (**stderr**) stream. Uses the **org.apache.logging.log4j.core.appender.ConsoleAppender** class by default.

FILE

Write log messages to a file.

Uses the `org.apache.logging.log4j.core.appender.RollingFileAppender` class by default.

JSON-FILE

Write log messages to a file in JSON format.

Uses the `org.apache.logging.log4j.core.appender.RollingFileAppender` class by default.

14.1.5. Log Patterns

The `CONSOLE` and `FILE` appenders use a `PatternLayout` to format the log messages according to a **pattern**.

An example is the default pattern in the `FILE` appender:

```
%d{yyyy-MM-dd HH:mm:ss,SSS} %-5p (%t) [%c{1}] %m%throwable%n
```

- `%d{yyyy-MM-dd HH:mm:ss,SSS}` adds the current time and date.
- `%-5p` specifies the log level, aligned to the right.
- `%t` adds the name of the current thread.
- `%c{1}` adds the short name of the logging category.
- `%m` adds the log message.
- `%throwable` adds the exception stack trace.
- `%n` adds a new line.

Patterns are fully described in [the `PatternLayout` documentation](#).

14.1.6. Enabling and Configuring the JSON Log Handler

Infinispan provides a JSON log handler to write messages in JSON format.

Prerequisites

- Stop Infinispan Server if it is running.
You cannot dynamically enable log handlers.

Procedure

1. Open `$ISPN_HOME/server/conf/log4j2.xml` with any text editor.
2. Uncomment the `JSON-FILE` appender and comment out the `FILE` appender:

```
<!--<AppenderRef ref="FILE"/>-->  
<AppenderRef ref="JSON-FILE"/>
```

3. Optionally configure the JSON appender and JSON layout as required.
4. Save and close `log4j2.xml`.

When you start Infinispan, it writes each log message as a JSON map in the following file:

`$ISPN_HOME/server/log/server.log.json`

Additional resources

- [RollingFileAppender](#)
- [JSONLayout](#)

14.2. Access Logs

Access logs record all inbound client requests for Hot Rod and REST endpoints to files in the `$ISPN_HOME/server/log` directory.

`org.infinispan.HOTROD_ACCESS_LOG`

Logging category that writes Hot Rod access messages to a `hotrod-access.log` file.

`org.infinispan.REST_ACCESS_LOG`

Logging category that writes REST access messages to a `rest-access.log` file.

14.2.1. Enabling Access Logs

To record Hot Rod and REST endpoint access messages, you need to enable the logging categories in `log4j2.xml`.

Procedure

1. Open `$ISPN_HOME/server/conf/log4j2.xml` with any text editor.
2. Change the level for the `org.infinispan.HOTROD_ACCESS_LOG` and `org.infinispan.REST_ACCESS_LOG` logging categories to `TRACE`.
3. Save and close `log4j2.xml`.

```
<Logger name="org.infinispan.HOTROD_ACCESS_LOG" additivity="false" level="TRACE">
  <AppenderRef ref="HR-ACCESS-FILE"/>
</Logger>
```

14.2.2. Access Log Properties

The default format for access logs is as follows:

```
%X{address} %X{user} [%d{dd/MM/yyyy:HH:mm:ss Z}] &quot;%X{method} %m
%X{protocol}&quot;; %X{status} %X{requestSize} %X{responseSize} %X{duration}%n
```

The preceding format creates log entries such as the following:

```
127.0.0.1 - [DD/MM/YYYY:HH:MM:SS +0000] "PUT /rest/v2/caches/default/key HTTP/1.1" 404 5 77 10
```

Logging properties use the `%X{name}` notation and let you modify the format of access logs. The following are the default logging properties:

Property	Description
<code>address</code>	Either the <code>X-Forwarded-For</code> header or the client IP address.
<code>user</code>	Principal name, if using authentication.
<code>method</code>	Method used. <code>PUT</code> , <code>GET</code> , and so on.
<code>protocol</code>	Protocol used. <code>HTTP/1.1</code> , <code>HTTP/2</code> , <code>HOTROD/2.9</code> , and so on.
<code>status</code>	An HTTP status code for the REST endpoint. <code>OK</code> or an exception for the Hot Rod endpoint.
<code>requestSize</code>	Size, in bytes, of the request.
<code>responseSize</code>	Size, in bytes, of the response.
<code>duration</code>	Number of milliseconds that the server took to handle the request.



Use the header name prefixed with `h:` to log headers that were included in requests; for example, `%X{h:User-Agent}`.

14.3. Audit Logs

Audit logs let you track changes to your Infinispan environment so you know when changes occur and which users make them. Enable and configure audit logging to record server configuration events and administrative operations.

`org.infinispan.AUDIT`

Logging category that writes security audit messages to an `audit.log` file in the `$ISPN_HOME/server/log` directory.

14.3.1. Enabling Audit Logging

To record security audit messages, you need to enable the logging category in `log4j2.xml`.

Procedure

1. Open `$ISPN_HOME/server/conf/log4j2.xml` with any text editor.
2. Change the level for the `org.infinispan.AUDIT` logging category to `INFO`.
3. Save and close `log4j2.xml`.

```
<!-- Set to INFO to enable audit logging -->
<Logger name="org.infinispan.AUDIT" additivity="false" level="INFO">
  <AppenderRef ref="AUDIT-FILE"/>
</Logger>
```

14.3.2. Configuring Audit Logging Appenders

Apache Log4j provides different appenders that you can use to send audit messages to a destination other than the default log file. For instance, if you want to send audit logs to a syslog daemon, JDBC database, or Apache Kafka server, you can configure an appender in `log4j2.xml`.

Procedure

1. Open `$ISPN_HOME/server/conf/log4j2.xml` with any text editor.
2. Comment or remove the default `AUDIT-FILE` rolling file appender.

```
<!--RollingFile name="AUDIT-FILE"
...
</RollingFile-->
```

3. Add the desired logging appender for audit messages.

For example, you could add a logging appender for a Kafka server as follows:

```
<Kafka name="AUDIT-KAFKA" topic="audit">
  <PatternLayout pattern="%date %message"/>
  <Property name="bootstrap.servers">localhost:9092</Property>
</Kafka>
```

4. Save and close `log4j2.xml`.

Additional resources

- [Log4j Appenders](#)

14.3.3. Using Custom Audit Logging Implementations

You can create custom implementations of the `org.infinispan.security.AuditLogger` API if configuring Log4j appenders does not meet your needs.

Prerequisites

- Implement `org.infinispan.security.AuditLogger` as required and package it in a JAR file.

Procedure

1. Add your JAR to the `server/lib` directory in your Infinispan Server installation.
2. Specify the fully qualified class name of your custom audit logger as the value for the `audit-logger` attribute on the `authorization` element in your cache container security configuration.

For example, the following configuration defines `my.package.CustomAuditLogger` as the class for logging audit messages:

```
<infinispan>
  <cache-container>
    <security>
      <authorization audit-logger="my.package.CustomAuditLogger"/>
    </security>
  </cache-container>
</infinispan>
```

Additional resources

- [org.infinispan.security.AuditLogger](#)

Chapter 15. Enabling and configuring Infinispan statistics and JMX monitoring

Infinispan can provide Cache Manager and cache statistics as well as export JMX MBeans.

15.1. Enabling statistics in remote caches

Infinispan Server automatically enables statistics for the default cache manager. However, you must explicitly enable statistics for your caches.

Procedure

1. Open your Infinispan configuration for editing.
2. Add the `statistics` attribute or field and specify `true` as the value.
3. Save and close your Infinispan configuration.

Remote cache statistics

XML

```
<distributed-cache statistics="true" />
```

JSON

```
{
  "distributed-cache": {
    "statistics": "true"
  }
}
```

YAML

```
distributed-cache:
  statistics: true
```

15.2. Enabling Hot Rod client statistics

Hot Rod Java clients can provide statistics that include remote cache and near-cache hits and misses as well as connection pool usage.

Procedure

1. Open your Hot Rod Java client configuration for editing.
2. Set `true` as the value for the `statistics` property or invoke the `statistics().enable()` methods.
3. Export JMX MBeans for your Hot Rod client with the `jmx` and `jmx_domain` properties or invoke the

`jmxEnable()` and `jmxDomain()` methods.

4. Save and close your client configuration.

Hot Rod Java client statistics

ConfigurationBuilder

```
ConfigurationBuilder builder = new ConfigurationBuilder();
builder.statistics().enable()
    .jmxEnable()
    .jmxDomain("my.domain.org")
.addServer()
    .host("127.0.0.1")
    .port(11222);
RemoteCacheManager remoteCacheManager = new RemoteCacheManager(builder.build());
```

hotrod-client.properties

```
infinispan.client.hotrod.statistics = true
infinispan.client.hotrod.jmx = true
infinispan.client.hotrod.jmx_domain = my.domain.org
```

15.3. Configuring Infinispan metrics

Infinispan generates metrics that are compatible with the MicroProfile Metrics API.

- Gauges provide values such as the average number of nanoseconds for write operations or JVM uptime.
- Histograms provide details about operation execution times such as read, write, and remove times.

By default, Infinispan generates gauges when you enable statistics but you can also configure it to generate histograms.

Procedure

1. Open your Infinispan configuration for editing.
2. Add the `metrics` element or object to the cache container.
3. Enable or disable gauges with the `gauges` attribute or field.
4. Enable or disable histograms with the `histograms` attribute or field.
5. Save and close your client configuration.

Metrics configuration

XML

```
<infinispan>
  <cache-container statistics="true">
    <metrics gauges="true"
      histograms="true" />
  </cache-container>
</infinispan>
```

JSON

```
{
  "infinispan" : {
    "cache-container" : {
      "statistics" : "true",
      "metrics" : {
        "gauges" : "true",
        "histograms" : "true"
      }
    }
  }
}
```

YAML

```
infinispan:
  cacheContainer:
    statistics: "true"
  metrics:
    gauges: "true"
    histograms: "true"
```

Verification

Infinispan Server exposes statistics through the `metrics` endpoint. You can collect metrics with any monitoring tool that supports the OpenMetrics format, such as Prometheus.

Infinispan metrics are provided at the `vendor` scope. Metrics related to the JVM are provided in the `base` scope.

You can retrieve metrics from Infinispan Server as follows:

```
$ curl -v http://localhost:11222/metrics
```

To retrieve metrics in MicroProfile JSON format, do the following:

```
$ curl --header "Accept: application/json" http://localhost:11222/metrics
```

- [Eclipse MicroProfile Metrics](#)

15.4. Registering JMX MBeans

Infinispan can register JMX MBeans that you can use to collect statistics and perform administrative operations. You must also enable statistics otherwise Infinispan provides 0 values for all statistic attributes in JMX MBeans.

Procedure

1. Open your Infinispan configuration for editing.
2. Add the `jmx` element or object to the cache container and specify `true` as the value for the `enabled` attribute or field.
3. Add the `domain` attribute or field and specify the domain where JMX MBeans are exposed, if required.
4. Save and close your client configuration.

JMX configuration

XML

```
<infinispan>
  <cache-container statistics="true">
    <jmx enabled="true"
        domain="example.com"/>
  </cache-container>
</infinispan>
```

JSON

```
{
  "infinispan" : {
    "cache-container" : {
      "statistics" : "true",
      "jmx" : {
        "enabled" : "true",
        "domain" : "example.com"
      }
    }
  }
}
```

```

infinispan:
  cacheContainer:
    statistics: "true"
  jmx:
    enabled: "true"
    domain: "example.com"

```

15.4.1. Enabling JMX remote ports

Provide unique remote JMX ports to expose Infinispan MBeans through connections in JMXServiceURL format.



Infinispan Server does not expose JMX remotely via the single port endpoint. If you want to remotely access Infinispan Server via JMX you must enable a remote port.

Procedure

- Pass the following system properties to Infinispan at startup:

```

-Dcom.sun.management.jmxremote
-Dcom.sun.management.jmxremote.port=9999
-Dcom.sun.management.jmxremote.authenticate=false
-Dcom.sun.management.jmxremote.ssl=false

```

15.4.2. Infinispan MBeans

Infinispan exposes JMX MBeans that represent manageable resources.

org.infinispan:type=Cache

Attributes and operations available for cache instances.

org.infinispan:type=CacheManager

Attributes and operations available for cache managers, including Infinispan cache and cluster health statistics.

For a complete list of available JMX MBeans along with descriptions and available operations and attributes, see the *Infinispan JMX Components* documentation.

Additional resources

- [Infinispan JMX Components](#)

15.4.3. Registering MBeans in custom MBean servers

Infinispan includes an `MBeanServerLookup` interface that you can use to register MBeans in custom MBeanServer instances.

Prerequisites

- Create an implementation of `MBeanServerLookup` so that the `getMBeanServer()` method returns the custom `MBeanServer` instance.
- Configure Infinispan to register JMX MBeans.

Procedure

1. Open your Infinispan configuration for editing.
2. Add the `mbean-server-lookup` attribute or field to the JMX configuration for the cache manager.
3. Specify fully qualified name (FQN) of your `MBeanServerLookup` implementation.
4. Save and close your client configuration.

JMX MBean server lookup configuration

XML

```
<cache-container statistics="true">
  <jmx enabled="true"
    domain="example.com"
    mbean-server-lookup="com.example.MyMBeanServerLookup" />
</cache-container>
```

JSON

```
{
  "infinispan" : {
    "cache-container" : {
      "statistics" : "true",
      "jmx" : {
        "enabled" : "true",
        "domain" : "example.com",
        "mbean-server-lookup" : "com.example.MyMBeanServerLookup"
      }
    }
  }
}
```

YAML

```
infinispan:
  cacheContainer:
    statistics: "true"
  jmx:
    enabled: "true"
    domain: "example.com"
    mbeanServerLookup: "com.example.MyMBeanServerLookup"
```

Chapter 16. Retrieving Health Statistics

Monitor the health of your Infinispan clusters in the following ways:

- Programmatically with `embeddedCacheManager.getHealth()` method calls.
- JMX MBeans
- Infinispan REST Server

16.1. Accessing the Health API via JMX

Retrieve Infinispan cluster health statistics via JMX.

Procedure

1. Connect to Infinispan server using any JMX capable tool such as JConsole and navigate to the following object:

```
org.infinispan:type=CacheManager,name="default",component=CacheContainerHealth
```

2. Select available MBeans to retrieve cluster health statistics.

16.2. Accessing the Health API via REST

Get Infinispan cluster health via the REST API.

Procedure

- Invoke a **GET** request to retrieve cluster health.

```
GET /rest/v2/cache-managers/{cacheManagerName}/health
```

Infinispan responds with a **JSON** document such as the following:

```
{
  "cluster_health":{
    "cluster_name":"ISPN",
    "health_status":"HEALTHY",
    "number_of_nodes":2,
    "node_names":[
      "NodeA-36229",
      "NodeB-28703"
    ]
  },
  "cache_health":[
    {
      "status":"HEALTHY",
      "cache_name":"___protobuf_metadata"
    },
    {
      "status":"HEALTHY",
      "cache_name":"cache2"
    },
    {
      "status":"HEALTHY",
      "cache_name":"mycache"
    },
    {
      "status":"HEALTHY",
      "cache_name":"cache1"
    }
  ]
}
```



Get cache manager status as follows:

```
GET /rest/v2/cache-managers/{cacheManagerName}/health/status
```

Reference

See the *REST v2 (version 2) API* documentation for more information.

Chapter 17. Performing rolling upgrades for Infinispan Server clusters

Perform rolling upgrades of your Infinispan clusters to change between versions without downtime or data loss and migrate data over the Hot Rod protocol.

17.1. Setting up target Infinispan clusters

Create a cluster that uses the Infinispan version to which you plan to upgrade and then connect the source cluster to the target cluster using a remote cache store.

Prerequisites

- Install Infinispan Server nodes with the desired version for your target cluster.



Ensure the network properties for the target cluster do not overlap with those for the source cluster. You should specify unique names for the target and source clusters in the JGroups transport configuration. Depending on your environment you can also use different network interfaces and port offsets to separate the target and source clusters.

Procedure

1. Create a remote cache store configuration, in JSON format, that allows the target cluster to connect to the source cluster.

Remote cache stores on the target cluster use the Hot Rod protocol to retrieve data from the source cluster.

```

{
  "remote-store": {
    "cache": "myCache",
    "shared": true,
    "raw-values": true,
    "security": {
      "authentication": {
        "digest": {
          "username": "username",
          "password": "changeme",
          "realm": "default"
        }
      }
    }
  },
  "remote-server": [
    {
      "host": "127.0.0.1",
      "port": 12222
    }
  ]
}

```

2. Use the Infinispan Command Line Interface (CLI) or REST API to add the remote cache store configuration to the target cluster so it can connect to the source cluster.

- CLI: Use the `migrate cluster connect` command on the target cluster.

```

[//containers/default]> migrate cluster connect -c myCache --file=remote
-store.json

```

- REST API: Invoke a POST request that includes the remote store configuration in the payload with the `rolling-upgrade/source-connection` method.

```

POST /v2/caches/myCache/rolling-upgrade/source-connection

```

3. Repeat the preceding step for each cache that you want to migrate.
4. Switch clients over to the target cluster, so it starts handling all requests.
 - a. Update client configuration with the location of the target cluster.
 - b. Restart clients.

Additional resources

- [Remote cache store configuration schema](#)

17.2. Synchronizing data to target clusters

When you set up a target Infinispan cluster and connect it to a source cluster, the target cluster can handle client requests using a remote cache store and load data on demand. To completely migrate data to the target cluster, so you can decommission the source cluster, you can synchronize data. This operation reads data from the source cluster and writes it to the target cluster. Data migrates to all nodes in the target cluster in parallel, with each node receiving a subset of the data. You must perform the synchronization for each cache that you want to migrate to the target cluster.

Prerequisites

- Set up a target cluster with the appropriate Infinispan version.

Procedure

1. Start synchronizing each cache that you want to migrate to the target cluster with the Infinispan Command Line Interface (CLI) or REST API.
 - CLI: Use the `migrate cluster synchronize` command.

```
[//containers/default]> migrate cluster synchronize -c myCache
```

- REST API: Use the `?action=sync-data` parameter with a POST request.

```
POST /v2/caches/myCache?action=sync-data
```

When the operation completes, Infinispan responds with the total number of entries copied to the target cluster.

2. Disconnect each node in the target cluster from the source cluster.
 - CLI: Use the `migrate cluster disconnect` command.

```
[//containers/default]> migrate cluster disconnect -c myCache
```

- REST API: Invoke a DELETE request.

```
DELETE /v2/caches/myCache/rolling-upgrade/source-connection
```

Next steps

After you synchronize all data from the source cluster, the rolling upgrade process is complete. You can now decommission the source cluster.

Chapter 18. Patching Infinispan Server Installations

Install and manage patches for Infinispan Server installations.

You can apply patches to multiple Infinispan Server installations with different versions to upgrade to a desired target version. However, patches do not take effect if Infinispan Server is running. If you want to upgrade Infinispan clusters without downtime, create a new cluster with the target version and perform a rolling upgrade to that version instead of patching.

18.1. Infinispan Server Patches

Infinispan Server patches are `.zip` archives that contain artifacts that you can apply to your `$ISPN_HOME` directory to fix issues and add new features.

Patches also provide a set of rules for Infinispan to modify your server installation. When you apply patches, Infinispan overwrites some files and removes others, depending on if they are required for the target version.

However, Infinispan does not make any changes to configuration files that you have created or modified when applying a patch. Server patches do not modify or replace any custom configuration or data.

18.2. Creating Server Patches

You can create patches for Infinispan Server from an existing installation.

You can create patches for Infinispan Server starting from version 10.1.7. You can patch any 10.1 or later server installation. However you cannot patch 9.4.x or earlier servers with 10.1.7 or later.

You can also create patches that either upgrade or downgrade the Infinispan Server version. For example, you can create a patch from version 10.1.7 and use it to upgrade version 10.1.5 or downgrade version 11.0.0.

Procedure

1. Navigate to `$ISPN_HOME` for a Infinispan Server installation that has the target version for the patch you want to create.
2. Start the CLI.

```
$ bin/cli.sh  
[disconnected]>
```

3. Use the `patch create` command to generate a patch archive and include the `-q` option with a meaningful qualifier to describe the patch.

```
[disconnected]> patch create -q "this is my test patch" path/to/mypatch.zip \  
path/to/target/server/home path/to/source/server/home
```

The preceding command generates a `.zip` archive in the specified directory. Paths are relative to `$ISPN_HOME` for the target server.

Create single patches for multiple different Infinispan versions, for example:



```
[disconnected]> patch create -q "this is my test patch"  
path/to/mypatch.zip \  
path/to/target/server/home \  
path/to/source/server1/home path/to/source/server2/home
```

Where `server1` and `server2` are different Infinispan versions where you can install "mypatch.zip".

4. Describe the generated patch archive.

```
[disconnected]> patch describe path/to/mypatch.zip
```

```
Infinispan patch target=$target_version(my test patch) source=$source_version  
created=$timestamp
```

- `$target_version` is the Infinispan version from which the patch was created.
- `$source_version` is one or more Infinispan versions to which you can apply the patch.

You can apply patches to Infinispan Server installations that match the `$source_version` only.

18.3. Installing Server Patches

Apply patches to Infinispan Server to upgrade or downgrade an existing version.

Prerequisites

- Create a server patch for the target version.

Procedure

1. Navigate to `$ISPN_HOME` for the Infinispan Server installation you want to patch.
2. Stop the Infinispan Server if it is running.



If you patch a server while it is running, the version changes take effect after restart. If you do not want to stop the server, create a new cluster with the target version and perform a rolling upgrade to that version instead of patching.

3. Start the CLI.

```
$ bin/cli.sh  
[disconnected]>
```

4. Install the patch.

```
[disconnected]> patch install path/to/patch.zip  
  
Infinispan patch target=$target_version source=$source_version \  
created=$timestamp installed=$timestamp
```

- `$target_version` displays the Infinispan version that the patch installed.
- `$source_version` displays the Infinispan version before you installed the patch.

5. Start the server to verify the patch is installed.

```
$ bin/server.sh  
...  
ISPN080001: Infinispan Server $version
```

If the patch is installed successfully `$version` matches `$target_version`.



Use the `--server` option to install patches in a different `$ISPN_HOME` directory, for example:

```
[disconnected]> patch install path/to/patch.zip  
--server=path/to/server/home
```

18.4. Rolling Back Server Patches

Remove patches from Infinispan Server by rolling them back and restoring the previous Infinispan version.



If a server has multiple patches installed, you can roll back the last installed patch only.

Rolling back patches does not revert configuration changes you make to Infinispan Server. Before you roll back patches, you should ensure that your configuration is compatible with the version to which you are rolling back.

Procedure

1. Navigate to `$ISPN_HOME` for the Infinispan Server installation you want to roll back.

2. Stop the server if it is running.
3. Start the CLI.

```
$ bin/cli.sh  
[disconnected]>
```

4. List the installed patches.

```
[disconnected]> patch ls  
  
Infinispan patch target=$target_version source=$source_version  
created=$timestamp installed=$timestamp
```

- `$target_version` is the Infinispan server version after the patch was applied.
- `$source_version` is the version for Infinispan server before the patch was applied. Rolling back the patch restores the server to this version.

5. Roll back the last installed patch.

```
[disconnected]> patch rollback
```

6. Quit the CLI.

```
[disconnected]> quit
```

7. Start the server to verify the patch is rolled back to the previous version.

```
$ bin/server.sh  
...  
ISPN080001: Infinispan Server $version
```

If the patch is rolled back successfully `$version` matches `$source_version`.



Use the `--server` option to rollback patches in a different `$ISPN_HOME` directory, for example:

```
[disconnected]> patch rollback --server=path/to/server/home
```

Chapter 19. Troubleshooting Infinispan Servers

Gather diagnostic information about Infinispan server deployments and perform troubleshooting steps to resolve issues.

19.1. Getting Diagnostic Reports for Infinispan Servers

Infinispan servers provide aggregated reports in `tar.gz` archives that contain diagnostic information about both the Infinispan server and the host. The report provides details about CPU, memory, open files, network sockets and routing, threads, in addition to configuration and log files.

Procedure

1. Create a CLI connection to Infinispan.
2. Use the `server report` command to download a `tar.gz` archive:

```
[//containers/default]> server report
Downloaded report 'infinispan-<hostname>-<timestamp>-report.tar.gz'
```

3. Move the `tar.gz` file to a suitable location on your filesystem.
4. Extract the `tar.gz` file with any archiving tool.

19.2. Changing Infinispan Server Logging Configuration at Runtime

Modify the logging configuration for Infinispan servers at runtime to temporarily adjust logging to troubleshoot issues and perform root cause analysis.

Modifying the logging configuration through the CLI is a runtime-only operation, which means that changes:

- Are not saved to the `log4j2.xml` file. Restarting server nodes or the entire cluster resets the logging configuration to the default properties in the `log4j2.xml` file.
- Apply only to the nodes in the cluster when you invoke the CLI. Nodes that join the cluster after you change the logging configuration use the default properties.

Procedure

1. Create a CLI connection to Infinispan.
2. Use the `logging` to make the required adjustments.
 - List all appenders defined on the server:

```
[//containers/default]> logging list-appenders
```


The preceding command returns:

```
{
  "STDOUT" : {
    "name" : "STDOUT"
  },
  "JSON-FILE" : {
    "name" : "JSON-FILE"
  },
  "HR-ACCESS-FILE" : {
    "name" : "HR-ACCESS-FILE"
  },
  "FILE" : {
    "name" : "FILE"
  },
  "REST-ACCESS-FILE" : {
    "name" : "REST-ACCESS-FILE"
  }
}
```

- List all logger configurations defined on the server:

```
[//containers/default]> logging list-loggers
```

The preceding command returns:

```
[ {
  "name" : "",
  "level" : "INFO",
  "appenders" : [ "STDOUT", "FILE" ]
}, {
  "name" : "org.infinispan.HOTROD_ACCESS_LOG",
  "level" : "INFO",
  "appenders" : [ "HR-ACCESS-FILE" ]
}, {
  "name" : "com.arjuna",
  "level" : "WARN",
  "appenders" : [ ]
}, {
  "name" : "org.infinispan.REST_ACCESS_LOG",
  "level" : "INFO",
  "appenders" : [ "REST-ACCESS-FILE" ]
} ]
```

- Add and modify logger configurations with the `set` subcommand

For example, the following command sets the logging level for the `org.infinispan` package to `DEBUG`:

```
[//containers/default]> logging set --level=DEBUG org.infinispan
```

- Remove existing logger configurations with the `remove` subcommand.

For example, the following command removes the `org.infinispan` logger configuration, which means the root configuration is used instead:

```
[//containers/default]> logging remove org.infinispan
```

19.3. Resource Statistics

You can inspect server-collected statistics for some of the resources within a Infinispan server using the `stats` command.

Use the `stats` command either from the context of a resource which collects statistics (containers, caches) or with a path to such a resource:

```
[//containers/default]> stats
{
  "statistics_enabled" : true,
  "number_of_entries" : 0,
  "hit_ratio" : 0.0,
  "read_write_ratio" : 0.0,
  "time_since_start" : 0,
  "time_since_reset" : 49,
  "current_number_of_entries" : 0,
  "current_number_of_entries_in_memory" : 0,
  "total_number_of_entries" : 0,
  "off_heap_memory_used" : 0,
  "data_memory_used" : 0,
  "stores" : 0,
  "retrievals" : 0,
  "hits" : 0,
  "misses" : 0,
  "remove_hits" : 0,
  "remove_misses" : 0,
  "evictions" : 0,
  "average_read_time" : 0,
  "average_read_time_nanos" : 0,
  "average_write_time" : 0,
  "average_write_time_nanos" : 0,
  "average_remove_time" : 0,
  "average_remove_time_nanos" : 0,
  "required_minimum_number_of_nodes" : -1
}
```

```
[//containers/default]> stats /containers/default/caches/mycache
{
  "time_since_start" : -1,
  "time_since_reset" : -1,
  "current_number_of_entries" : -1,
  "current_number_of_entries_in_memory" : -1,
  "total_number_of_entries" : -1,
  "off_heap_memory_used" : -1,
  "data_memory_used" : -1,
  "stores" : -1,
  "retrievals" : -1,
  "hits" : -1,
  "misses" : -1,
  "remove_hits" : -1,
  "remove_misses" : -1,
  "evictions" : -1,
  "average_read_time" : -1,
  "average_read_time_nanos" : -1,
  "average_write_time" : -1,
  "average_write_time_nanos" : -1,
  "average_remove_time" : -1,
  "average_remove_time_nanos" : -1,
  "required_minimum_number_of_nodes" : -1
}
```